

Creating Flow Frames for Posters, Brochures or Magazines using flowfram.sty version 2.2

Nicola L.C. Talbot

Dickimaw Books
`dickimaw-books.com`

2026-04-25

This document is also available as HTML (`flowfram-manual.html`).



Version 2.0 has been mostly rewritten using \LaTeX 3 commands and updated to take into account changes to the output routine in the \LaTeX kernel. Some defaults have changed. If there are any compatibility issues you can rollback to v1.18 or v1.17. For example:



```
\usepackage{flowfram}[=v1.18]
```

Note that v1.18 was never publicly released but is just a minor change to v1.17 to allow for rollback with corrections.

The rollback files are frozen snapshots of older versions. Bear in mind that those old versions may not work properly with new kernels.

List of Examples

v

Contents

1. Introduction	1
1.1. Frame Stacking Order	4
1.2. Package Options	9
1.2.1. Thumbtabs, Contents and Mini-Tocs	10
1.2.2. Dynamic Frames	17
1.2.3. Column Command Options	21
1.2.4. Other	24
1.3. Floats	27
1.4. Draft Mode	28
1.5. Output Routine	31
1.6. Chapters	32
2. Defining New Frames	35
2.1. Flow Frames	35
2.1.1. Prematurely Ending a Flow Frame	38
2.2. Static Frames	40
2.3. Setting the Contents	41
2.3.1. Continued Text	43
2.3.2. Important Notes	50
2.4. Dynamic Frames	50
2.4.1. Putting Chapter Titles in a Dynamic Frame	54
2.4.2. Putting Headers and Footers in a Dynamic Frame	60
2.4.3. Continued Text	65
2.4.4. Important Notes	67
3. Modifying Frame Attributes	69
3.1. Set Frame Options	70
3.1.1. Identification and Scope	71
3.1.2. Content Attributes	75

1

2

3

4

5

6

7

8

9



1	3.1.3. Layout Attributes	78
2	3.1.4. Appearance	85
3	3.1.5. HTML	89
4	3.2. Non-Rectangular Frames	91
5	3.3. Switching Frames On and Off On-The-Fly	94
6	4. Locations and Dimensions	101
7	4.1. Determining the Location of the Typeblock	101
8	4.2. Determining the Dimensions and Locations of Frames	103
9	4.3. Relative Locations	103
	5. Predefined Layouts	111
	5.1. Column Styles	111
	5.2. Column Styles with an Additional Frame	115
	5.3. Right to Left Columns	127
	5.4. Backdrop Effects	128
	5.4.1. Vertical stripe effects	129
	5.4.2. Horizontal stripe effect	130
	5.4.3. Background Frame	131
	5.4.4. Vertical and Horizontal Rules	132
	6. Thumbtabs and Minitocs	137
	6.1. Thumbtabs	137
	6.2. Minitocs	144
	7. Global Settings	147
	7.1. Macros	147
	7.2. Lengths	148
	7.3. Counters	149
	8. FlowframTk	153
	8.1. Export to Image	153

8.2.	Compute Parameters for <code>\parshape</code> or <code>\shapepar</code>	154
8.3.	Export to Document Class or Package	154
8.4.	The <code>flowframtkutils</code> Package	155
8.4.1.	Options	156
8.4.2.	Provided Commands	157
9.	Troubleshooting	179
9.1.	General Queries	179
9.2.	Unexpected Output	182
9.3.	Error Messages	184
A.	Glossary	187
A.1.	Terms	187
A.2.	Symbols	190
B.	Alphabetical Summaries	191
B.1.	Command Summary	191
	Command Summary: A	191
	Command Summary: B	192
	Command Summary: C	192
	Command Summary: D	194
	Command Summary: E	199
	Command Summary: F	200
	Command Summary: G	217
	Command Summary: H	219
	Command Summary: I	221
	Command Summary: J	224
	Command Summary: L	224
	Command Summary: M	225
	Command Summary: N	226
	Command Summary: O	231

Command Summary: P 235
Command Summary: R 235
Command Summary: S 236
Command Summary: T 244
Command Summary: V 250
B.2. Environment Summary 252

C. Package Option Summary 255

Index 265

If an example shows the icon  then the source code is embedded in the PDF as an attachment. If your PDF viewer supports attachments, you can extract the self-contained example file to try it out for yourself. Alternatively, you can click on the download icon  which will try downloading the example source code from your closest CTAN mirror, but make sure that this user manual matches the version on CTAN first. You can also try using:

```
texdoc -l flowfram-manual-example<nnn>
```

where $\langle nnn \rangle$ is the example number zero-padded to three digits to find out if the example files are installed on your device.

1.	Frame Page Lists	3
2.	Frame Stacking Order	8
3.	Continuation Text in Static Frames	50
4.	Two Columns in Draft Mode	113
5.	Rules	135

List of Examples



This document is the user manual for the flowfram package. Advanced users wanting further details of the package should read the documented code `flowfram-code.pdf`. Sample files are provided with the documentation.

The flowfram package is a \LaTeX package designed to enable you to create text frames in a document such that the contents of the document environment flow from one frame to the next in the order that they were defined. This is useful for creating posters or magazines or any other form of document that does not conform to the standard one or two column layout. There's an optional helper application called FlowframTk (distributed separately) if you prefer to use a graphical user interface to set up the document layout (see §7.3).

Each frame has an identification number (IDN) that's unique to the particular type of frame that may be used to identify it. You may also assign an identification label (IDL) for reference purposes to make it easier to remember. In general, a command or environment with both a starred and unstarred version that requires an ID will need the IDN for the unstarred version and the IDL for the starred version. Some commands may allow keywords (`all`, `odd` or `even`) instead of a numeric value for the unstarred versions.

The flowfram package tries to make \TeX do something it wasn't originally designed to do. It modifies the output routine and may not always perform as desired. Extra care must be taken if a paragraph spans frames of unequal width due to the asynchronous nature of \TeX 's output routine. (See §9.2.) The flowfram package has only been tested on a limited number of packages, and may well conflict with packages that also modify the output routine or rely on it being unmodified. You can switch back to the normal output routine with `\FlowFramRestoreOR` and then restore flowfram's modified output routine with `\FlowFramUnrestoreOR` if necessary (see §1.5).

If the geometry package is required, it's best to load it first and setup the page dimensions before flowfram is loaded. You can load geometry afterwards and the typeblock dimensions will automatically be updated after it has been loaded, but they won't be correct if you later change the settings with `\geometry`. The lengths governing the typeblock are:

1. Introduction

1.1.	Frame Stacking Order	4
1.2.	Package Options	9
1.2.1.	Thumbtabs, Contents and Mini-Tocs	10
1.2.2.	Dynamic Frames	17
1.2.3.	Column Command Options . . .	21
1.2.4.	Other	24
1.3.	Floats	27
1.4.	Draft Mode	28
1.5.	Output Routine	31
1.6.	Chapters	32

This chapter provides a brief overview of the package, the package options and the various frame types.

`\typeblockwidth`

The width of the typeblock. This is initialised to `\textwidth`.

`\typeblockheight`

The height of the typeblock. This is initialised to `\textheight`.

`\typeblockoffsety`

The vertical offset of the typeblock. This is initialised to the sum of `\topmargin`, `\headheight`, `\headsep` and `\voffset`.

These lengths identify the dimensions and vertical offset of the typeblock to ensure that all defined frames are in the correct relative positions. If these dimensions change then the available area used by commands like `\onecolumn`, `\twocolumn` and `\Ncolumn` might be incorrect.

The geometry package's `showframes` option will be confused by `flowfram`'s frames. You can instead use `flowfram`'s `draft` option to show the layout.

If you need to switch frames on and off, it's best to use the `pages=absolute` package option if the page counter is reset in the document.

Example 1 creates three flow frames. The first is labelled "single" (only shown on absolute page 1), and the other two are labelled "left" and "right" (shown on all pages except the first). The example also creates a dynamic frame labelled "sidepanel" that's shown on all pages (the default page list setting). The `draft` package option is used to show the outlines of each frame and the typeblock. The flow frames created with `\onecolumn`



and `\twocolumn` are slightly shorter than the typeblock due to the default adjustment setting (see §5.1).

Example 1: Frame Page Lists



1

```
\documentclass[11pt]{book}
\usepackage[a4paper,outer=3in,marginparwidth=2cm,
columnsep=4pt]{geometry}
\usepackage[pages=absolute,draft]{flowfram}
\usepackage{lipsum}% provide dummy text
\pagestyle{plain}
\onecolumn[1][single]% only use on page 1
\setflowframe*{single}{margin=inner}
\twocolumn[>1][left,right]% all pages except p.1
\setflowframe*{left}{margin=left}
\setflowframe*{right}{margin=right}
\newdynamicframe{2in}{\typeblockheight}
% width & height
{\typeblockwidth+\columnsep}{0pt}% position
[sidepanel]% label
\newcommand{\Hugebf}{\Huge\bfseries}
\setdynamicframe*{sidepanel}
{evenx={-2in-\columnsep}, style={Hugebf}}
\setdynamiccontents*{sidepanel}{Side Panel on
Page \thepage.}
\begin{document}
First page.\marginpar{note1}
\mainmatter
Start sample.\marginpar{note2} \lipsum[3-5]
End sample.\marginpar{note3}
\end{document}
```



Note that this example document has narrow columns with a small gap between them. This can cause overfull lines and a cramped layout, but it's for illustrative purposes only.




Figure 1.1.: Frame Layers

In Example 1 the page counter is reset by `\mainmatter` (which also does `\clear-doublespage`). With `pages=relative`, the page list “1” refers to any page where the page counter is 1 so the “single” flow frame would be used on both the first and third page and the “left” and “right” flow frames (which have page list >1) wouldn’t be selected on the third page but would still be selected on the second page. However, with `pages=absolute` the page lists now refer to the absolute page.

The `flowfram` package provides three types of frame: flow frames, static frames and dynamic frames, each with a custom width, height and position. (These may be changed later, see §2.4.4.) The main contents of the document environment flow from one flow frame to the next in the order of definition (for the flow frames that are valid on the current page), whereas the contents of the static and dynamic frames are set explicitly using commands such as `\setstaticcontents` (see §2.2) and `\setdynamiccontents` (see §2.4).



Unless otherwise stated, all co-ordinates are relative to the bottom left hand corner of the typeblock. If you have a two-sided document, the absolute position of the typeblock may vary depending on the values of `\oddsidemargin` and `\evensidemargin`, and all the frames will shift accordingly unless otherwise indicated. Alternative positions for even pages can be set with the `evenx` and `eveny` attributes but those co-ordinates are still relative to the position of the even page typeblock.

The page list (`pages`), exclusion list (`excludepages`), and the `hide` and `hidethis` settings determine whether or not a frame is valid for a particular page.

1.1. Frame Stacking Order

The material on each page is placed in the following order:

1. Each static frame that’s valid for the current page in ascending order of IDN (shown in magenta in figure 1.1).

2. Each flow frame that's valid for the current page in ascending order of IDN (shown in yellow in figure 1.1).
3. Each dynamic frame that's valid for the current page in ascending order of IDN (shown in cyan in figure 1.1).
4. Bounding boxes if the `draft` package option has been used.

This ordering can be used to determine if you want something to overlay or underlay everything else on the page. Note that the frames do not interact with each other. If you have two or more overlapping frames, the text in each frame will not attempt to wrap around the other frames, but will simply overwrite them.

For non-rectangular frames, see §3.2. (That is, normal static or dynamic frames that have their content shaped using `\parshape` or `\shapepar/\Shapepar`.)

Example 2 demonstrates the layers with a strange overlapping layout. Note that this example is intentionally weird and is not a recommendation!

First, some flow frames are defined. I've given them labels to make them easier to reference when changing their attributes:

```
\newflowframe
{0.4\typeblockwidth}% width
{0.6\typeblockwidth}% height
{0pt}% x
{0.6\typeblockwidth}% y
[upper]% label
\setflowframe*{upper}{border=plain}

\newflowframe
```

```

{0.4\typeblockwidth}% width
{0.6\typeblockwidth}% height
{0.6\typeblockwidth}% x
{0pt}% y
[lower]% label
\setflowframe*{lower}{border=shadowbox}

\newflowframe
{0.4\typeblockwidth}% width
{0.6\typeblockwidth}% height
{0.3\typeblockwidth}% x
{0.3\typeblockwidth}% y
[middle]% label
\setflowframe*{middle}{background=yellow}

```

This will need the fancybox package for the `\shadowbox` command. (More complex borders can be created with tikz or using FlowframTk.)

Order of definition matters. The above are defined in the order: upper (IDN 1), lower (IDN 2), and middle (IDN 3). This means that the document text will start in upper, flow into lower, and then into middle.

A custom counter helps to demonstrate the order in which contents are processed:

```
\newcounter{sample}
```

Next a dynamic frame is defined:

```
\newdynamicframe
{0.5\typeblockwidth}% width
{0.5\typeblockwidth}% height
{0.75\typeblockwidth}% x
{0.25\typeblockwidth}% y
[sample]% label
```

The contents are then set so that the sample counter is incremented and shown, and an image (provided by mwe) is displayed (this will need the graphicx package):


```
\setdynamiccontents*{sample}{%
\hfill\stepcounter{sample}
Sample \thesample\_\_ (dynamic) .\par
\includegraphics[width=\linewidth]
{example-image-a}
}
```

Labels are unique to the particular frame's *type*. A static frame is defined in a similar way and, in this case, it happens to have the same label (`sample`) as the dynamic frame. This isn't a problem as they are different types of frame. However, it can be a bit confusing.

```
\newstaticframe
{0.5\typeblockwidth}% width
{0.5\typeblockwidth}% height
{0.5\typeblockwidth}% x
{0.4\typeblockwidth}% y
[sample]% label
```

1. Introduction

Example 2: Frame Stacking Order



The document uses the lipsum package to provide sample text:

```
START.  
(sample \stepcounter{sample}\thesample) .  
\lipsum[1-2]  
END.
```

Frames must be defined in the preamble, but the contents of static or dynamic frames may be set in the document body. This example sets the `sample` static frame content after the sample text (but it's still on page 1):

```
\setstaticcontents*{sample}{%  
  \stepcounter{sample}  
  Sample \thesample\_(static).\par  
  \includegraphics[width=\linewidth]  
    {example-image-b}  
}
```

Some things to note from Example 2:

- The static frame has its contents set in a box register, which means that the `sample` counter is incremented as soon as the contents are set, but `\setstaticcontents` was placed at the end of the one-paged document. The first increment of the `sample` counter occurs at the start of the first paragraph of the document text, so the counter has the value 1 when `\setstaticcontents` is processed. Therefore the contents of the static frame shows “Sample 2”.

Static frames are always positioned on the page first, so the sample static frame is drawn first and is partially obscured by the other frames with overlapping positions. Although the flow frames were filled first (because the document text came before `\setstaticcontents`), they are still drawn on top of the static frame.

- The document text automatically flows into the flow frames (using a similar mechanism to the way the standard two-column mode works). However the column order is determined by the order of definition of the flow frames. In this example, the order leads to the document text starting at the top left, continuing in the bottom right, and then moving into the middle of the page. Flow frames are always positioned after static frames so the middle and lower frames obscure the static frame that has an overlapping position.
- The dynamic frame has its contents stored in a token list variable which isn't expanded until the output routine positions it on the page so, although the frame contents were set in the preamble, the sample counter increment in the dynamic frame contents doesn't take effect until the end of the current page. Dynamic frames are always positioned after the other types of frame, so the sample dynamic frame obscures the others with overlapping positions.
- If more content is added to the document text before `\setstaticcontents` then the first page may be completed before the contents of the static frame are set. In which case, the "B" image won't show until the next page and the sample counter increment won't occur until after it has been incremented by the dynamic frame when the first page is shipped.

So it's important to consider the order when defining frames but it's also important to consider the frame type and when and how the different types of frame are filled and processed.

1.2. Package Options

```
\usepackage[<options>]{flowfram}
```



Some options may only be set when the package is loaded, some may be set in the preamble (before any command affected by the setting is used) and a few may be used anywhere. For those options that may be changed after the package has loaded, you can set them with:

```
\flowframsetup{<key=value list>}
```



Available options are listed in the sections below or see §9.3 for an alphabetical list.

1.2.1. Thumbtabs, Contents and Mini-Tocs

Thumbtabs are dynamic frames with a special label that can be created with `\make-thumbtabs` (see §6.1). If enabled, they correspond to a particular sectioning unit (such as chapter), with the frame's content set to the number or the title or both. These dynamic frames are aligned against the edge of the page and are designed to be shown only in the applicable sectioning unit.

Each thumbtab frame has a corresponding index frame which may be shown in the table of contents. This requires adjusting the `\tableofcontents` command to show the index frames. The relevant sub-block in the table of contents may be adjusted so that it fills the height of the corresponding thumbtab index frame



No thumbtabs information will be written to the `ttb` file until they are first enabled with `\enablethumbtabs`. This can later be suspended with `\disable-thumbtabs`. While the thumbtabs are disabled, options such as `unstarred-thumbtabs` and `matter-thumbtabs` will have no effect.

Mini-tocs are a sub-set of the table of contents that may be displayed at the start of the applicable sectioning unit. This may or may not be the same unit as the thumbtabs (if also present). The default is to match them if both thumbtabs and mini-tocs are required.

The mini-toc information is obtained when flowfram's modified `\tableofcontents` parses the `toc` file.

This means that if the `adjust-toc=off` option is used to restore the `\tableofcontents` definition that's in effect when flowfram is first loaded, then neither mini-tocs nor thumbtab indexes can be supported.

adjust-toc=*<setting>*

Specifies whether `\tableofcontents` should be adjusted to allow for thumbtab indexes and mini-tocs. This may take one of the following values:

adjust-toc=**header**

Adjust the table of contents, including the header. This may change the way the page header is displayed, if a page style with headers is used.

adjust-toc=**noheader**

Adjust the table of contents, but not the header.

adjust-toc=**off**

Don't adjust the table of contents. There's no support for thumbtab indexes or mini-tocs with this setting.

backmatter-sections=*<setting>*

initial: **no-number**

Classes that support `\backmatter` tend to suppress the chapter number but not section numbers. As this can cause interference, flowfram by default adds code to `\backmatter` that sets `secnumdepth` to `-1`. This option may be used to prevent this.

`backmatter-sections=no-change`

If `\backmatter` is defined, `flowfram`'s additional code won't alter `secnumdepth`.

`backmatter-sections=no-number`

Make `\backmatter` (if defined) set `secnumdepth` to `-1`.

`toc-thumbtabs=⟨setting⟩`

*default: **true**; initial: **false***

Indicates whether or not thumbtab indexes should be shown in `\tableofcontents` and whether or not to align them. Note that the alignment setting should only be used if the table of contents is on a single page. It's not appropriate for longer content. This setting has no effect with `adjust-toc=off`.

`toc-thumbtabs=aligned`

Divide the table of contents into blocks that are the same height as the corresponding thumbtab. This assumes that the start of the table of contents is aligned with the vertical offset identified when the thumbtabs were created. If the thumbtabs are shifted too far up or down the `⟨y-offset⟩` will need to be adjusted in the first optional argument of `\make-thumbtabs`. This setting is only applicable for singled-paged table of contents.

`toc-thumbtabs=unaligned`

Don't align the sub-block in the table of contents with the corresponding thumbtab and only show the thumbtab indexes on the first page of the table of contents.

toc-thumbtabs=true

Show the thumbtab indexes on every page of the table of contents.

toc-thumbtabs=false

Don't show the thumbtab indexes in the table of contents.

unstarred-thumbtabs=*<boolean>* *default: true; initial: false*

Indicates whether or not unstarred sectional units should have thumbtabs. Note that this is not the same as unstarred but unnumbered sectional units in the front matter or back matter. (See `matter-thumbtabs` below, for that.)

This option will have no effect if thumbtabs aren't enabled when the applicable sectional units occur.

matter-thumbtabs=*<setting>*

Indicates if unstarred sectional units outside of the main matter should have thumbtabs. Unstarred commands such as `\chapter` are not usually numbered outside of the main matter but behave slightly differently to the starred version. For example, `\chapter` without a star may not be numbered but may be added to the table of contents. This setting does not affect the starred version.

This setting will have no effect if thumbtabs aren't enabled outside of the main matter.

matter-thumbtabs=main-only

Only support thumbtabs for unstarred (numbered) units in the main matter.



```
matter-thumbtabs=all
```

Support thumbtabs for all unstarred units.




```
matter-thumbtabs=not-front
```

Only support thumbtabs for unstarred (numbered) units in the main matter and back matter but not in the front matter.




```
matter-thumbtabs=not-back
```

Only support thumbtabs for unstarred (numbered) units in the main matter and front matter but not in the back matter.



```
thumtbat-links=<setting>
```

Indicates which thumbtabs should have `\hyperlinks` (if supported). You will need to load `hyperref` if you want `\hyperlinks`.



```
thumtbat-links=toc-only
```

Only have `\hyperlinks` in the thumtbat indexes that are shown in the table of contents.



```
thumtbat-links=all
```

Have `\hyperlinks` in all the thumbtabs.

thumbtab-links=none

Don't have \hyperlinks in any of the thumbtabs.

thumbtab-text=⟨setting⟩

initial: **rotate**

Indicates how the text should be shown on the thumbtabs.

thumbtab-text=rotate

Turn the text sideways. This will either rotate the text to the right or to the left, depending on whether or not a two-sided layout is on and whether or not the current page is odd or even.

thumbtab-text=rotate-right

Rotate the text to the right.

thumbtab-text=rotate-left

Rotate the text to the left.

thumbtab-text=stack

Stacks the letters vertically. This doesn't look very good and is just provided for backward-compatibility.

thumbtab-text=normal

No rotation or stacking.

thumbtabs= $\langle setting \rangle$

preamble only

Indicates whether or not the number or title should be shown in the thumbtabs (if enabled).

thumbtabs=**title**

Only show the title.

thumbtabs=**number**

Only show the number (if applicable).

thumbtabs=**both**

Show both the number (if applicable) and the title

thumbtabs=**none**

Don't show either the number or title.

sections-extra-option= $\langle setting \rangle$

The flowfram package redefines the standard sectioning commands so that they have a second optional argument (which is used for the corresponding thumbtab title, if enabled), but it first saves the original definitions to use as an underlying command. Normally it will only pass the first optional argument to the underlying command.

If you are using a class, such as memoir, that also has a second optional argument, then this option identifies whether or not the second optional argument should also be passed to

the underlying command. If flowfram detects that memoir has been loaded, it will automatically implement `sections-extra-option=original-and-thumbtab` otherwise it will implement `sections-extra-option=thumbtab-only`.

`sections-extra-option=thumbtab-only`

Only use the second optional argument as the thumbtab title (if applicable) and don't pass it to the underlying command.

`sections-extra-option=original-and-thumbtab`

The underlying command has a second optional argument and any second optional argument should be both passed to the underlying command and used as the thumbtab title (if enabled).

`sections-extra-option=as-original`

The underlying command has a second optional argument and any second optional argument provided should simply be passed to the underlying command and not used as the thumbtab title.

1.2.2. Dynamic Frames

`dynamic-page-style=<setting>`

initial: **adjust**
preamble only

Indicates whether or not `\makedfheaderfooter` should adjust the standard page styles. If this option is required, it should be set before `\makedfheaderfooter` otherwise it will be too late to have an effect.

dynamic-page-style=adjust

If `\makedfheaderfooter` is used, it will set (`\let`) the `empty`, `plain`, `headings` and `myheadings` page styles to `ffempty`, `ffplain`, `ffheadings` and `ffmyheadings`.

dynamic-page-style=noadjust

Don't adjust the page styles.

dynamic-header-case=⟨setting⟩

initial: no-change

Indicates whether or not `\chaptermark` (if chapters are defined) or `\sectionmark` (otherwise) with the `ffheadings` and `ffmyheadings` styles should change the case of the header text.

dynamic-header-case=uc

Convert to uppercase.

dynamic-header-case=no-change

Don't change the case.

dynamic-subheader-case=⟨setting⟩

initial: no-change

Indicates whether or not `\sectionmark` (if chapters are defined) or `\subsectionmark` (otherwise) with the `ffheadings` and `ffmyheadings` styles should change the case of the sub-header text.

dynamic-subheader-case=uc

Convert to uppercase.

dynamic-subheader-case=no-change

Don't change the case.

dynamic-page-style-header-font= $\{ \langle code \rangle \}$ *initial: \emph*

Use the given $\langle code \rangle$ to set the font used by `\chaptermark` (if chapters are available) or `\sectionmark` (otherwise) with `ffheadings`. The $\langle code \rangle$ may be declarations or the final command in $\langle code \rangle$ may be a text-block command.

If $\langle code \rangle$ is empty (but the equal sign = will still be required) no font change will be applied. For example, you may prefer to use the dynamic frame's `style` command instead.

dynamic-page-style-subheader-font= $\{ \langle code \rangle \}$

Use the given $\langle code \rangle$ to set the font used by `\sectionmark` (if chapters are available) or `\subsectionmark` (otherwise) with `ffheadings`. The $\langle code \rangle$ may be declarations or the final command in $\langle code \rangle$ may be a text-block command. Again the $\langle code \rangle$ may be empty.

The sub-header font is initialised to match the header font, so if you change the header font it will automatically change the sub-header font as well.

dynamic-empty-page-style= { *<value>* }

initial: **hide**

Controls how the **ffempty** page style behaves with dynamic header and footer frames. Remember that with the default **dynamic-page-style=adjust**, **\makedf-headerfooter** will set the **empty** page style to **ffempty**. The initial setting is **dynamic-empty-page-style=empty**, **dynamic-empty-page-style=hide**. This means that **dynamic-empty-page-style=show** will revert back to showing empty frames.

If you have decorated the header or footer dynamic frame, such as setting a border or background colour, then simply setting the header and footer to empty (the usual behaviour of the **empty** page style), the header and footer frames will still be visible. This may or may not be desired.

dynamic-empty-page-style=empty

The **ffempty** page style will set the header and footer text to empty but the frames will still be visible. This option automatically sets **dynamic-empty-page-style=show**.

dynamic-empty-page-style=plain

The **ffempty** page style will behave like the **ffplain** style. The header and footer frames will be visible. This option automatically sets **dynamic-empty-page-style=show**.

dynamic-empty-page-style=headings

The **ffempty** page style will behave like the **ffheadings** style. The header and footer frames will be visible. This option automatically sets **dynamic-empty-page-style=show**.

`dynamic-empty-page-style=myheadings`

The `fempty` page style will behave like the `fmyheadings` style. The header and footer frames will be visible.

`dynamic-empty-page-style=ignore`

The `fempty` page style will do nothing, so the previous page style will remain in effect. The header and footer frames will be visible. This option automatically sets `dynamic-empty-page-style=show`.

`dynamic-empty-page-style=hide`

The header and footer frames will have the `hide` attribute set by the `fempty` page style. No other change will be made, but since the frames will no longer be shown, the frame content won't be visible.

Note that if `\thispagestyle` is used instead of `\pagestyle` then `hidethis` instead of `hide` will be set.

`dynamic-empty-page-style=show`

The header and footer frames won't have the `hide` (or `hidethis`) attribute set by the `fempty` page style. Whatever `dynamic-empty-page-style` setting was in effect before `dynamic-empty-page-style=hide` will continue.

1.2.3. Column Command Options

These options govern column commands, such as `\onecolumn`, `\onecolumninarea`, `\twocolumn` and `\twocolumninarea`, which create one or more flow

frames arranged as columns (see §5.1). This includes column commands that additionally create a frame to go above or below the column flow frames (see §5.2).

The order that the flow frames are defined matters, as the output routine selects the next flow frame in order of definition (that is, in ascending order of IDN) and cycles back to the start when a page is shipped out. So if the first flow frame to be defined is on the left, the document text will start on the left, but if the first flow frame to be defined is on the right, then the document text will start on the right.

LR ≡
preamble only

The column commands, such as `\twocolumn`, will create flow frames from left to right. This is the default.

RL ≡
preamble only

The column commands, such as `\twocolumn`, will create flow frames from right to left. The **RL** option may be set in the preamble but should be set before the applicable commands are used (see also §5.3).

column-changes=*⟨setting⟩* ≡
initial: ignore

The `flowfram` package redefines `\onecolumn` and `\twocolumn` for use in the preamble to define a single flow frame (`\onecolumn`) or two flow frames (`\twocolumn`). However, some commands provided by the kernel or other classes or packages may try to use `\onecolumn` and `\twocolumn` to adjust the page layout. This option indicates what to do if these commands are encountered in the document environment.

`column-changes=ignore`

Ignore any instance of `\onecolumn` or `\twocolumn` found in the document environment. In the case of `\twocolumn`, if the optional argument is present, it will simply be added to the page content.

`column-changes=clearpage`

Like `column-changes=ignore` but does `\clearpage`.

`column-changes=switch`

Switch to the designated frames, which will first need to be identified. If you use `\onecolumn` or `\onecolumninarea` in the preamble (see §5.1), the first instance will automatically identify the flow frame to use for any `\onecolumn` found in the document. Alternatively, you can identify the required flow frame with:

`\SetOneColumnFrame{⟨ID⟩}`

modifier: *

The `⟨ID⟩` should be the frame's IDN for the unstarred version or the IDL for the starred version.

Similarly if you use `\twocolumn` or `\twocolumninarea`, the first instance will automatically identify the flow frames to use for any `\twocolumn` found in the document. However, this is a little more complicated as a frame for the header and shorter columns are also needed in the event that `\twocolumn` is used with its optional argument. Commands such as `\twocolumnStop` or `\twocolumnDtop` will identify the frames to use in this case. You can also identify the desired frames with:

```
\SetTwoColumnFrames [⟨header-type⟩] [⟨header-id⟩] {⟨col-1⟩}
[⟨header-col1⟩] {⟨col-2⟩} [⟨header-col-2⟩] modifier: *
```

The starred version references the frames by their IDL. The unstarred version references them by their IDN.

The first non-headed flow frame is identified by *⟨col1⟩* and the second non-headed flow frame is identified by *⟨col2⟩*. If the optional arguments are omitted, then this just establishes the two flow frames to use.

To identify a frame for the header and the two flow frames accompanying it, the optional arguments are required: *⟨header-type⟩* is the frame type for the header (*flow*, *dynamic* or *static*). Note that dynamic frames are best for this, although they can cause dependent counters to go out-of-sync. The header frame is identified with *⟨header-id⟩*. The first headed flow frame is identified with *⟨header-col1⟩* and the second headed flow frame is identified with *⟨header-col2⟩*.

If you don't identify the designated frames to use, you will get a warning.

1.2.4. Other

```
pages=⟨setting⟩ initial: relative  
preamble only
```

All frames have an associated page list that determines which pages they should be shown on. By default, this uses the page counter, but as that is sometimes reset (for example, when changing from front matter to main matter) this can be ambiguous. Version 1.14 introduced the *absolute* page counter which is incremented every time a page is shipped out and should not be reset, which allows for unambiguous references in the page lists.

pages=absolute

Use the absolute page counter.

pages=relative

Use the standard page counter. Note that the page lists always uses the numeric value (1, 2, etc) not the formatted value (i, ii, etc). This is the default setting for backward compatibility.

adjust-pre-chapter=*<boolean>* *default: true; initial: true*
package option only

If true and `\chapter` is defined, the pre-chapter hook commands `\ffprechapterhook` and `\chapterfirstpagestyle` will be defined (see §1.6).

verbose=*<boolean>* *default: true; initial: false*

Switches on or off verbose mode. Provided to assist with debugging.

draft

Switches on draft mode (see §1.4).

final

Switches off draft mode.

prohibit-frame-rotation=*<boolean>* default: **true**; initial: **false**

If true, don't rotate frames, regardless of the **angle** setting.
The remaining options are provided for backward-compatibility.

norotate

Equivalent to setting both **prohibit-frame-rotation**=true and **thumbtab-text**=stack. The original version of flowfram was released in 2005 when there was less support for rotation, so the default was no frame rotation and no thumbtab text rotation. This is no longer applicable, so this is no longer the default.

rotate=*<boolean>* default: **true**; initial: **false**

If true, this option is equivalent to setting both **prohibit-frame-rotation**=false and **thumbtab-text**=rotate-right. If false, this option is equivalent to **norotate**.

ttbtitle

preamble only

Include the title in the thumbtabs (if enabled). This doesn't affect whether or not the number is shown. Use the **thumbtabs** option instead.

ttbnotitle

preamble only

Don't include the title in the thumbtabs (if enabled). This doesn't affect whether or not the number is shown. Use the **thumbtabs** option instead.

ttbnum

preamble only

Include the number in the thumbtabs (if enabled). This doesn't affect whether or not the title is shown. Use the `thumbtabs` option instead.

ttbnonum

preamble only

Don't include the number in the thumbtabs (if enabled). This doesn't affect whether or not the title is shown. Use the `thumbtabs` option instead.

color=*<boolean>**default: true; initial: true*
preamble only

If true, enable colour support. Note that the color package is now always loaded regardless of this option but setting this value to false will prevent the `textcolor`, `backcolor` and `bordercolor` frame options from having an effect.

nocolor

preamble only

Equivalent to `color=false`.


1.3. Floats

The standard figure and table commands will behave as usual in the flow frames, but their starred versions, `figure*` and `table*` behave no differently from figure and table. This is

because the arbitrary layout of the flow frames makes it difficult to determine where to put them.


If you really need floats to behave normally on a particular page, you can temporarily restore the normal output routine with `\FlowFramRestoreOR` (see §1.5). Note that all the defined frame won't be used until you revert back to `flowfram`'s output routine with `\FlowFramUnrestoreOR`.

Since floats can't go in the content of static frames or dynamic frames, the `flowfram` package provides two environments that may be used instead. Unlike their figure and table counterparts, they are fixed in place, and so do not take an optional placement specifier.



```
\begin{staticfigure}
<content>
\end{staticfigure}
```

Simulate a figure in a static or dynamic frame.



```
\begin{statictable}
<content>
\end{statictable}
```

Simulate a table in a static or dynamic frame.

The `\caption` and `\label` commands can be used within `staticfigure` and `statictable` as usual, but remember that if the frame is displayed on multiple pages, you may end up with multiply defined labels. You may want to consider setting the `clear` attribute to automatically clear the frame contents on every page.

1.4. Draft Mode

The `flowfram` package's `draft` option will draw the bounding boxes for each frame that has been defined. At the bottom right of each bounding box (except for the bounding box

denoting the typeblock), a marker will be shown in the form: $[\langle T \rangle : \langle IDN \rangle ; \langle IDL \rangle]$, where $\langle T \rangle$ is a single letter denoting the frame type, $\langle IDN \rangle$ is the IDN for the frame and $\langle IDL \rangle$ is the IDL for that frame. Values of $\langle T \rangle$ are: F (flow frame), S (static frame) or D (dynamic frame). Markers of the form: $[M : \langle IDN \rangle]$ indicate that the bounding box is the area taken up by the margin for flow frame with IDN $\langle IDN \rangle$.

The bounding box will not be rotated, even if a frame has rotation set.

There are conditionals that govern what types of bounding boxes should be shown. The `draft` option sets all these conditionals to true. You can instead selectively switch on or off the applicable conditions instead of using `draft` or in addition to using `draft`.

```
\ifshowtypeblock <true>\else <false>\fi      initial: \iffalse
```

Determines whether or not the bounding box for the typeblock should be shown.

```
\showtypeblocktrue
```

Show the typeblock bounding box.

```
\showtypeblockfalse
```

Don't show the typeblock bounding box.

```
\ifshowmargins <true>\else <false>\fi      initial: \iffalse
```

Determines whether or not the bounding box for the margins should be shown.

```
\showmarginstrue
```

Show the margin bounding box.

```
\showmarginsfalse
```

Don't show the margin bounding box.

```
\ifshowframebbox <true>\else <false>\fi    initial: \iffalse
```

Determines whether or not the bounding box for the frames should be shown.

```
\showframebboxtrue
```

Show the bounding box for all frames.

```
\showframebboxfalse
```

Don't show the bounding box for all frames.

You can see the layout for the current page (irrespective of whether or not the `draft` option has been set) using the command:

```
\flowframeshowlayout
```

This finishes the current page, temporarily sets draft mode, and prints an empty page. Only the frames for that page will be shown.

`\flowframeshowlayout` shows the frames for the page *after* the current page.

1.5. Output Routine

The `flowfram` package modifies the output routine to ensure that all frames are placed in the correct location and that `\textwidth` and `\textheight` and related dimensions are correctly set. In particular, it removes the page header and footer code from their normal place to allow for the header and footer to be placed in dynamic frames with arbitrary dimensions and locations.

This can cause a conflict with other packages that rely on an unaltered output routine or expect `\textwidth` and `\textheight` to reflect the one column size. For example, the `geometry` package's `showframes` option will be confused and may draw the outline of the `typeblock` shorter or narrower than it ought to be, which will consequently push the footer frame out of place. Therefore, if you want to view the page layout, use `flowfram`'s `draft` option instead.

If you need to use a command or environment that requires the normal output routine, you can restore it with:

`\FlowFramRestoreOR`

not preamble

This will finish the current page (with `\finishthispage`) and setup a normal one column page layout with `\textheight` set to `\typeblockheight` and `\textwidth` set to `\typeblockwidth`. The `absolutepage` counter will still be incremented in the `build/page/after` hook but none of the static frames, flow frames or dynamic frames will appear on the page. The header and footer will be restored to their usual

location. The `figure*` and `table*` environments and `\onecolumn` and `\twocolumn` commands will also be restored to normal.

You can later revert back to `flowfram`'s output routine with:

```
\FlowFramUnrestoreOR
```

not preamble

This will start a new page (using `\clearpage`) and select the first flow frame that's valid for the new page. The `figure*` and `table*` environments will once again behave like their unstarred counterparts. Likewise `\onecolumn` and `\twocolumn` will return to their document environment behaviour.

1.6. Chapters

If the `\chapter` command has been defined, the `flowfram` package will add the following commands to the `cmd/chapter/before` hook:

```
\ffprechapterhook
\thispagestyle{\chapterfirstpagestyle}
```

Note that these two `flowfram` commands won't be defined if `\chapter` hasn't been defined or if `adjust-pre-chapter=false` has been used.

These hooks are largely redundant now that there are more convenient hooks provided with the new `LATEX` hook management system, but they are retained for backward-compatibility.

```
\ffprechapterhook
```

initial: empty

Does nothing by default.

`\chapterfirstpagestyle`

initial: plain



Expands to the page style name to use for the first page of each chapter.

If you want to use a different style, you will need to redefine `\chapterfirstpagestyle` to the name of the relevant page style. Note that some classes provide their own way of adjusting the style of the first page of each chapter.



These hooks are used at the start of `\chapter` *before* `\clearpage` or `\cleardoublepage` is called.

Chapter titles can be placed in a dynamic frame. See §2.4.1 for further details.

There are three types of frame: flow frames, static frames and dynamic frames. They each have their own set of commands to define a new frame and to set the frame’s attributes. Their identifying labels (IDLs) and numbers (IDNs) are unique to each type of frame. For example, the first flow frame to be defined will have IDN 1, but the first static frame and the first dynamic frame will also have IDN 1.

2.1. Flow Frames

The flow frame is the principle type of frame. The text of the document environment will flow from one frame to the next in order of definition. Each flow frame has an associated width, height, position on the page and optionally a border.

A flow frame’s width and height must be greater than 0pt. This is checked by commands like `\newflowframe`, which will trigger an error for invalid dimensions but is not checked if the width or height is later changed with commands like `\setflowframe`. Not only will zero-width flow frames cause overfull hbox warnings but also if all defined flow frames have zero width then the output routine may end up creating thousands of pages that can’t be filled.

`\newflowframe` [*⟨page-list⟩*] {*⟨width⟩*} {*⟨height⟩*} {*⟨x⟩*} {*⟨y⟩*} [*⟨label⟩*]
modifier: *
preamble only

Defines a new flow frame, where *⟨width⟩* is the width of the frame, *⟨height⟩* is the height of the frame, (*⟨x⟩*, *⟨y⟩*) is the position of the bottom left hand corner of the frame relative to the bottom left hand corner of the typeblock.

The starred version will add a plain border to the frame, which is simply a shortcut for first defining the frame and then setting the `border=plain` attribute.

2. Defining New Frames

2.1. Flow Frames 35
2.1.1. Prematurely Ending a Flow Frame 38
2.2. Static Frames 40
2.3. Setting the Contents 41
2.3.1. Continued Text 43
2.3.2. Important Notes 50
2.4. Dynamic Frames 50
2.4.1. Putting Chapter Titles in a Dynamic Frame 54
2.4.2. Putting Headers and Footers in a Dynamic Frame 60
2.4.3. Continued Text 65
2.4.4. Important Notes 67

This chapter describes how to define new frames, and how to identify and set frame contents. See also §4.3.

See §4.1 if you need to calculate positions from the page edge.

The first optional argument, *⟨page list⟩*, indicates the list of pages for which this frame is defined. A page list can either be specified by the keywords: `all`, `odd`, `even` or `none`, or by a comma-separated list of either individual page numbers or page ranges. If *⟨page list⟩* is omitted, `all` is assumed. A page range can be a closed range (such as, `2–8`) or an open range (such as, `<10` or `>5`). For example: `<3, 5, 7–11, >15` indicates pages 1, 2, 5, 7, 8, 9, 10, 11 and all pages greater than page 15. These page numbers refer to the integer value of the page counter by default, so if you have a page *i* and a page 1, they will both have the same layout (unless you change the page list setting somewhere between the two pages).

With the `pages=absolute` package option, the numbers in the page list refer to the absolute page number (as given by the `absolute page counter`). In which case page 1 refers to the first page of the document only, regardless of whether there is another page 1 or page *i* later in the document.


You can't use formatted numbers (such as *i* or *I*) in the page list as `flowfram` needs the integer values in conditional expressions.

Each flow frame has its own unique IDN, corresponding to the order in which it was defined. So the first flow frame to be defined has IDN 1, the second has IDN 2, and so on. This number can then be used to identify the flow frame when you want to modify its settings. Alternatively, you can assign a unique IDL to the flow frame using the final optional argument *⟨label⟩*. If omitted, the IDL will be the same as its IDN.

```
\getflowlabel{⟨IDN⟩}
```

Expands to the IDL for the flow frame identified by its IDN. An error will occur if there is no flow frame with the given IDN.


There is no equivalent command that will expand to the IDN. Instead you need to fetch the value with:



```
\getflowid{<cmd>}{<IDL>}
```


This will define the command `<cmd>` to expand to the IDN of the flow frame identified by its IDL. An error will occur if there is no flow frame with the given IDL.

For example, suppose the first flow frame has been defined with:



```
\newflowframe{0.6\textwidth}{\textheight}{0pt}
{0pt}[main]
```

Then later in the document:



```
The label for the first
flow frame is
``\getflowlabel{1}``.
The flow frame labelled
``main`` has IDN
\getflowid{\myid}{main}
\myid.
```

```
The label for the first flow frame is
"main". The flow frame labelled "main"
has IDN 1.
```

If the document continues beyond the last defined flow frame (for example, the flow frames have only been defined on pages 1 to 10, but the document contains 11 pages) then a single flow frame will be defined, emulating one column mode for all subsequent pages.

Flow frame attributes can be changed with `\setflowframe`. See §2.4.4 for further details.

2.1.1. Prematurely Ending a Flow Frame

You can force text to move immediately to the next defined flow frame using `\newpage` or `\pagebreak`. These work in an analogous way to the way they work in standard two-column mode.


`\framebreak[$\langle n \rangle$]`

This command is required when a paragraph spans two flow frames of different widths, as \TeX 's output routine does not adjust to the new value of `\hsize` until the last paragraph of the previous column (flow frame in this case) has ended. As a result, the end of the paragraph at the beginning of the new flow frame retains the width of the previous flow frame. The optional argument is as for `\pagebreak`.

The `\framebreak` command is similar to `\newpage` in that it forces a break in the flow of the document text but, unlike `\newpage`, if `\framebreak` is used mid-paragraph it forces a break without given the appearance of a break in the paragraph.

The use of `\framebreak` can lead to unwanted excess space in the paragraph before the break.


If a paragraph spans two flow frames of unequal width without using `\framebreak` a warning will be issued. If a subtle difference in frame widths is caused by rounding errors (for example, if the frames were created using `FlowframTk`) you can adjust the tolerance to suppress these warnings.


`\fftolerance`*initial: 2pt*


The tolerance used when determining whether or not to warn when moving between flow frames of different widths is given by the length register `\fftolerance`. If you want to change the tolerance, you need to change the value of this register using an appropriate length command, such as `\setlength`. For example, to suppress warnings where the difference in width is less than 3pt, do:


`\setlength{\fftolerance}{3pt}`

If you want to start a new page, rather than simply move to the next flow frame, use the command `\clearpage`, or for two-sided documents, to start on the next odd page do `\cleardoublepage`.


`\cleartoevenpage`

This command is like `\cleardoublepage` but ensures that the next page is even.


`\finishthispage`

To finish the entire page (rather than just move to the next column), you can also use `\finishthispage`. This ensures that each remaining valid flow frame on the current page is shipped out with empty content.

2.2. Static Frames

A static frame is a rectangular area in which text neither flows into nor flows out of. That is, you have to explicitly set the contents of this frame. A static frame may have non-rectangular content (see §3.2).



A static frame may appear to contain text belonging to another frame if that other frame overlaps it. This doesn't mean that the static frame contains that text.

The contents must be set explicitly, and once set, the contents of the static frame will remain the same on each page until it is explicitly changed. Thus, a static frame can be used, for example, to make a company logo appear in the same place on every page. The `clear` attribute may be set to automatically clear the contents whenever a page is shipped out.



```
\newstaticframe[⟨page-list⟩]{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}
[⟨label⟩]                                     modifier: *
                                              preamble only
```

Defines a new static frame. The arguments are the same as for `\newflowframe`: `⟨width⟩` is the width of the static frame, `⟨height⟩` is the height of the frame, `(⟨x⟩,⟨y⟩)` is the position of the bottom left hand corner of the frame relative to the bottom left hand corner of the typeblock. The first optional argument, `⟨page list⟩`, indicates the page list for which this static frame should appear, and the final optional argument, `⟨label⟩` is a unique textual IDL which you can use to identify this static frame. If no label is specified, you can refer to this frame by its unique IDN. The first static frame to be defined has IDN 1, the second has IDN 2, and so on.

The starred version assigns a plain border to the frame, which is simply a shortcut for first defining the frame and then setting the `border=plain` attribute.

```
\getstaticlabel{⟨IDN⟩}
```

Expands to the IDL for the static frame identified by its IDN. An error will occur if there is no static frame with the given IDN.

There is no equivalent command that will expand to the IDN. Instead you need to fetch the value with:

```
\getstaticid{⟨cmd⟩}{⟨IDL⟩}
```

This will define the command `⟨cmd⟩` to expand to the IDN of the static frame identified by its IDL. An error will occur if there is no static frame with the given IDL.

For example:

```
The label for the first
static frame is
``\getstaticlabel{1}``.
The static frame labelled
``backleft`` has IDN
\getstaticid{\myid}
{backleft}\myid.
```

```
The label for the first static frame is
“backleft”. The static frame labelled
“backleft” has IDN 1.
```

2.3. Setting the Contents

```
\begin{staticcontents} [⟨options⟩] {⟨IDN⟩}
⟨content⟩
\end{staticcontents}
```

The contents of a particular static frame may be set within the `staticcontents` environment, where the static frame is identified by its IDN.

```
\begin{staticcontents*} [options] {IDL}
content
\end{staticcontents*}
```

The starred version identifies the static frame by its IDN instead. Both environments (as from v2.0) have an optional argument that may be used to locally set the frame's attributes (see §2.4.4).

```
\setstaticcontents[options]{ID}{content} modifier: *
```

A command alternative to the above environments. The `<ID>` argument is the IDN for the unstarred version and the IDL for the starred version. If the optional argument is provided, this becomes a shortcut for first setting the options and then setting the content. The definition internally uses `staticcontents` or `staticcontents*` as applicable.

Frame attributes are global variables.

For advanced users: Unlike dynamic frames, which store their contents in a global token list variable, static frames set their contents in a box. A box variable, `\staticframe`, is used for temporary storage when the content is set in an `lrbox` environment.

`flowfram/staticbox/before`

The hook `flowfram/staticbox/before` is used immediately before the `\staticframe` box is set.




```
flowfram/staticbox/after
```

The hook `flowfram/staticbox/after` is used immediately before the `\staticframe` box is set.

The actual box variable associated with the static frame contents is then set after the `flowfram/staticbox/after` hook. Since this always occurs within the `staticcontents` or `staticcontents*` environment (either explicitly or implicitly via `\setstaticcontents`), any changes made by the hooks will be scoped by the usual environment grouping.


2.3.1. Continued Text

Although text can't flow into or out of a static frame, it's possible to simulate this effect.



```
\continueonframe[text]{ID}
```

This command may be used when either setting the contents of a static frame or a dynamic frame. When the command is encountered, the content that follows will be placed in the identified frame. The frame type depends on the context. If `\continueonframe` is used while setting the content of a static frame then `<ID>` refers to another static frame. It will match the encapsulating command or environment. (For dynamic frames, see §2.4.3.)



This command forces a break in the text whilst at the same time trying to justify it, so overly large space may occur.

For example, if `\continueonframe` is used within the body of `staticcontents` then `<ID>` refers to the next static frame's IDN (since `staticcontents` references the frame by its IDN), but if `\continueonframe` is used within the body of `staticcontents*` then `<ID>` refers to the next static frame's IDL (since `staticcontents*` references the frame by its IDL).

This command is actually just a convenient shortcut where the behaviour is determined by the encapsulating command or environment. For example:

```
\begin{staticcontents}{1}
Some text...
\continueonframe[Continued/]{2}
Some more text...
\end{staticcontents}
```

This is simply a shortcut for:

```
\begin{staticcontents}{1}
Some text...
\ffcontinuedtextlayout{Continued/}
\end{staticcontents}
\begin{staticcontents}{2}
\ffstaticpostcontinued{1}{2}
Some more text...
\end{staticcontents}
```

Whereas:

```
\begin{staticcontents*}{leftframe}
Some text...
\continueonframe[Continued/]{rightframe}
Some more text...
\end{staticcontents*}
```

This is a shortcut for:

```
\begin{staticcontents*}{leftframe}
Some text...
\ffcontinuedtextlayout{Continued/}
\end{staticcontents*}
\begin{staticcontents*}{rightframe}
\ffstaticpostcontinued{⟨IDN1⟩}{⟨IDN2⟩}
Some more text...
\end{staticcontents*}
```

where $\langle IDN1 \rangle$ is the IDN of leftframe and $\langle IDN2 \rangle$ is the IDN of rightframe.

Bear in mind that this means that `\continueonframe` causes a change in scope so any local changes made before the command won't still be in effect after it.

The optional argument $\langle text \rangle$ specifies some continuation text to place at the end of the first frame. If $\langle text \rangle$ is omitted, then (for static frames) the default is:

```
\ffdefaultstaticcontinuetext{⟨IDN1⟩}{⟨IDN2⟩}
initial: \ffdefaultcontinuetext
```

where $\langle IDN1 \rangle$ is the IDN of the first static frame and $\langle IDN2 \rangle$ is the IDN of the continuation frame. Note that these arguments are always numeric, regardless of the encapsulating command or environment.

By default, `\ffdefaultstaticcontinuetext` ignores its arguments and simply expands to:

```
\ffdefaultcontinuetext
```

initial: empty

This does nothing by default. It's also used by `\ffdefaultdynamiccontinuetext` so if you do, for example:

```
\renewcommand{\ffdefaultcontinuetext}{Continued/}
```

then this text will be used as the default for both static frames and dynamic frames.

An empty optional argument in `\continueonframe` is not the same as omitting the optional argument. This has changed in version 2.0. In earlier versions, the default value was simply empty.

The formatting of the supplied $\langle text \rangle$ is applied by:

```
\ffcontinuedtextlayout{\langle text \rangle}
```

The default definition fills the paragraph so that the end is flush with the right margin and then typesets the $\langle text \rangle$ flush right on the next line encapsulated with:

```
\ffcontinuedtextfont{\langle text \rangle}
```

The default definition expands to `\emph{\small \langle text \rangle}`.

This assumes that it should appear as though no paragraph break occurs in the transition between the two frames. If you want a paragraph break you need to explicitly put one before and after `\continueonframe`.

For example:

```
\begin{staticcontents*}{frame1}
Some text in the first frame. (Let's
assume this frame is somewhere on the
left half of the page.)

\continueonframe[Continued on the right]{frame2}

This is some text in the second frame. (Let's
assume this frame is somewhere on the
right half of the same page.)
\end{staticcontents*}
```

Alternatively, just redefine `\ffcontinuedtextlayout` and `\ffdefaultpostcontinued`. However, there seems little point in using `\continueonframe` in this case. You may just as well use two `staticcontents` environments to set the contents separately.

The content of the continuation static frame will start with:

```
\ffstaticpostcontinued{<IDN1>}{<IDN2>}
initial: \ffdefaultpostcontinued
```

The first argument is the IDN of the previous frame (the frame at the point where `\continueonframe` occurs). The second argument is the IDN of the continuation frame.

Both arguments are always numeric irrespective of whether or not the starred or unstarred version of `staticcontents` or `\setstaticcontents` was used (the second argument is an integer variable whereas the first is the actual number).

The default definition simply ignores its arguments and expands to:

```
\ffdefaultpostcontinued
```

This just does:

```
\par \noindent \ignorespaces
```

which is what suppresses the normal paragraph indentation at the start of the continuation frame content.

The arguments of `\ffstaticpostcontinued` provides a way of referencing back to the previous frame.

Example 3 redefines the default definitions to use `\relativeframelocation` (see §4.3) but first some layout commands described in §5.2 are used to create a flow frame with a static frame above it and another flow frame with a static frame below it.



```
\onecolumnStopinarea{1in}
{0.5\typeblockwidth-10pt}{\typeblockheight}
{0pt}{0pt}
\setstaticframe{\value{maxstatic}}
{label=upper,border=plain}

\onecolumnSbottominarea{1in}
{0.5\typeblockwidth-10pt}{\typeblockheight}
{0.5\typeblockwidth+10pt}{0pt}
\setstaticframe{\value{maxstatic}}
```

```
{label=lower,border=plain,parindent=1em}
```

I've assigned IDLs to the static frames: `upper` for the first one and `lower` for the second one. I've also given both static frames a border to make them stand out. The second (`lower`) has also been given its own paragraph indentation rather than using the default (given by `\sdfparindent`).

Now the defaults are changed:

```
\renewcommand{\ffdefaultstaticcontinuetext}[2]{%
  Continued
  \relativeframelocation{static}{#2}{static}{#1}%
}
\renewcommand{\ffstaticpostcontinued}[2]{%
  \ffcontinuedtextlayout{%
    Continued from
    \relativeframelocation{static}{#1}{static}{#2}%
  }%
  \ffdefaultpostcontinued
}
```

and then content is added to both static frames but `\continueonframe` is used to transition between the two. The optional argument isn't present so the default will be used:

```
\begin{staticcontents*}{upper}
Some text...
\continueonframe{lower}
resuming where we left off...

Next paragraph.
```


 Example 3: Continuation Text in Static Frames


Some text in a static frame for illustrative purposes that needs to break off and continue later on and

Continued below right

Lorem ipsum dolor sit amet, consectetur adipiscing elit. Ut purus elit, vestibulum ut, placerat ac, adipiscing vitae, felis. Curabitur dictum gravida mauris. Nam arcu libero, nonummy eget, consectetur id, vulputate a, magna. Donec vehicula augue eu neque. Pellentesque habitant morbi tristique senectus et netus et malesuada fames ac turpis egestas. Mauris ut leo. Cras viverra metus rhoncus sem. Nulla et lectus vestibulum urna fringilla ultrices. Phasellus eu tellus sit amet tortor gravida placerat. Integer sapien est, iaculis in, pretium quis, viverra ac, nunc. Praesent eget sem vel leo ultrices bibendum. Aenean faucibus. Morbi dolor nulla, malesuada eu, pulvinar at, mollis ac, nulla. Curabitur auctor semper nulla. Donec varius orci eget risus. Duis nibh mi, congue eu, accumsan eleifend, sagittis quis, diam. Duis eget orci sit amet orci dignissim rutrum.

Nam dui ligula, fringilla a, euismod sodales, sollicitudin vel, wisi. Morbi auctor lorem non justo. Nam lacus libero, pretium at, lobortis vitae, ultricies et, tellus. Donec aliquet, tortor sed accumsan bibendum, erat ligula aliquet magna, vitae or-

nare odio metus a mi. Morbi ac orci et nisl hendrerit mollis. Suspendisse ut massa. Cras nec ante. Pellentesque a nulla. Cum sociis natoque penatibus et magnis dis parturient montes, nascetur ridiculus mus. Aliquam tincidunt urna. Nulla ullamcorper vestibulum turpis. Pellentesque cursus luctus mauris.

Nulla malesuada porttitor diam. Donec felis erat, congue non, volutpat at, tincidunt tristique, libero. Vivamus viverra fermentum felis. Donec nonummy pellentesque ante. Phasellus adipiscing semper elit. Proin fermentum massa ac quam. Sed diam turpis, molestie vitae, placerat a, molestie nec, leo. Maecenas lacinia. Nam ipsum ligula, eleifend at, accumsan nec, suscipit a, ipsum. Morbi blandit ligula feugiat magna. Nunc eleifend consequat lorem. Sed lacinia nulla vitae enim. Pellentesque tincidunt purus vel magna. Integer non enim. Praesent euismod nunc eu purus. Donec bibendum quam in tellus. Nullam cursus pulvinar lectus. Donec et mi. Nam vulputate metus eu enim. Vestibulum pellentesque felis eu massa.

Continued from above left
resuming where we left off this is text in another static frame elsewhere on the page.

Next paragraph.

```
\end{staticcontents*}
```

The lipsum package is used for filler text. Note that because of the narrow columns, there are some overfull lines.

2.3.2. Important Notes

When you set the contents of a static frame, the contents are immediately typeset and stored in a \TeX “box” until it is time to put the contents on the page. This means that if you use any information that varies throughout the document (such as the page number) the value that is current when you set the static frame’s contents will be the value used.

However, if `\label` is used inside a static frame, the label information will be written to the auxiliary file each time the static frame is displayed until the contents of that frame have been changed. This means that you may end up with multiply defined labels.

If you want to use cross-referencing commands, it’s better to use a dynamic frame instead of a static frame.


2.4. Dynamic Frames

A dynamic frame is similar to a static frame except that its contents are re-typeset on each page. As with static frames, a dynamic frame may have non-rectangular content (see §3.2).

A static frame stores its contents in a “box”, whereas a dynamic frame stores its contents in a token list variable. This means that verbatim content may be used in the body of the `staticcontents` environment but not in the body of the `dynamiccontents` environment (and likewise for the starred versions).

The contents must be set and will remain the same until changed. There are some special types of dynamic frames that have their content automatically set. The `clear` attribute may be set to automatically clear the contents whenever a page is shipped out but this may interfere with the special dynamic frames.


Special frames have special labels that should not be assigned to non-special dynamic frames: `header`, `footer`, `evenheader`, `evenfooter` (see §2.4.2), `thumbtab` $\langle n \rangle$, `thumbtabindex` $\langle n \rangle$, `eventhumbtab` $\langle n \rangle$, and `eventhumbtabindex` $\langle n \rangle$ (see §6.1).



```
\newdynamicframe [ page-list ] { width } { height } { x } { y }
[ label ] modifier: *  
preamble only
```

Defines a new dynamic frame. The arguments are the same as for `\newflowframe`: $\langle width \rangle$ is the width of the dynamic frame, $\langle height \rangle$ is the height of the frame, $(\langle x \rangle, \langle y \rangle)$ is the position of the bottom left hand corner of the frame relative to the bottom left hand corner of the typeblock. The first optional argument, $\langle page list \rangle$, indicates the page list for which this dynamic frame should appear, and the final optional argument, $\langle label \rangle$ is a unique textual IDL which you can use to identify this dynamic frame. If no label is specified, you can refer to this frame by its unique IDN. The first dynamic frame to be defined has IDN 1, the second has IDN 2, and so on.


The starred version assigns a plain border to the frame, which is simply a shortcut for first defining the frame and then setting the `border=plain` attribute.



```
\getdynamiclabel { IDN }
```

Expands to the IDL for the dynamic frame identified by its IDN. An error will occur if there is no dynamic frame with the given IDN.


There is no equivalent command that will expand to the IDN. Instead you need to fetch the value with:



```
\getdynamicid{⟨cmd⟩}{⟨IDL⟩}
```


This will define the command `⟨cmd⟩` to expand to the IDN of the dynamic frame identified by its IDL. An error will occur if there is no dynamic frame with the given IDL.

For example, if the first dynamic frame is defined as:



```
\newdynamicframe{0.38\textwidth}{\textheight}
{0.62\textwidth}{0pt}[chaphead]
```


then later in the document:



```
The label for the first
dynamic frame is
``\getdynamiclabel{1}``.
The dynamic frame labelled
``chaphead`` has IDN
\getdynamicid{\myid}
{chaphead}\myid.
```

The label for the first dynamic frame is “chaphead”. The dynamic frame labelled “chaphead” has IDN 1.

The contents of a dynamic frame may be set with either a command or an environment but, in either case, the content can’t include any verbatim material.



```
\setdynamiccontents[options]{⟨ID⟩}{⟨content⟩}  modifier: *
```

Sets the contents of the dynamic frame identified by `⟨ID⟩`. This should be the frame’s IDN for the unstarred versions and the IDL for the starred version. If `⟨options⟩` is present, the given attributes will be applied to the frame first.

Frame attributes are global variables.

```
\begin{dynamiccontents} [⟨options⟩] {⟨IDN⟩}
⟨content⟩
\end{dynamiccontents}
```

Sets the contents of the dynamic frame identified by its IDN. If *⟨options⟩* is present, the given attributes will be applied to the frame first.

```
\begin{dynamiccontents*} [⟨options⟩] {⟨IDL⟩}
⟨content⟩
\end{dynamiccontents*}
```

The starred version is the same as `dynamiccontents` except that the frame is identified by its IDL.

Unlike static frames, you can append content to a dynamic frame.

```
\appenddynamiccontents[options]{⟨ID⟩}{⟨content⟩}
modifier: *
```

Appends *⟨content⟩* to the current content of the dynamic frame identified by its IDN (unstarred version) or by its IDL (starred version).

The dynamic frame content is stored in a global variable. It's not used until the output routine positions it on the page so there's no point localising any changes.

2.4.1. Putting Chapter Titles in a Dynamic Frame

If `\chapter` is defined, you can make the chapter heading appear in a dynamic frame instead of in its usual place in the flow of document text. There is no facility for placing other sectional types in a dynamic frame.

This feature was originally implemented with `\dfchaphead` which hacked the internal commands commonly used in the definition of `\chapter` but this is problematic and doesn't work with some classes so version 2.0 provides a new approach. The old `\dfchaphead` command is still available but its use is now deprecated.



The chapter heading refers to the (typically large, bold) text with the chapter number (if applicable) and title that's normally placed at the start of a new page. If you want thumbtabs, see §6.1. If you want page headers and footers in a dynamic frame, see §2.4.2.



`\ChapterInDynamic{⟨ID⟩}`

*modifier: **

Places the chapter heading in the dynamic frame identified by `⟨ID⟩`, which is the frame's IDN (unstarred) or IDL (starred). This command is only available if `\chapter` is defined.




This causes each instance of `\chapter` to set the contents of the identified dynamic frame which will replace any previous content.

The `flowfram` package redefines all the standard sectioning commands (`\chapter` is only redefined if it's already defined). The modified `\chapter` places the original definition in the content of the chosen dynamic frame, but there are some problems with this approach. Normally, the contents of a dynamic frame aren't expanded until the output

routine positions the frame on the page, and since dynamic frames are always positioned after flow frames this can cause counters and labels to be out-of-sync.

To avoid this problem, `\ChapterInDynamic` ensures that the chapter heading is first expanded by putting it in a box of the same width as the dynamic frame, but it first needs to locally disable problematic commands, such as `\clearpage`. This means that the page break usually performed by `\chapter` is now implemented with:



```
\dfchapterclearpage
```

This is be defined to use either `\clearpage` or `\cleardoublepage`, depending on the standard `openright` setting. This command is only available if `\chapter` is defined.

There are hooks available in the event that there are other problematic commands that may need adjusting. These hooks are only defined if `\chapter` is defined.



```
flowfram/chaphead/before
```

The `flowfram/chaphead/before` hook is used before the heading box is set but after the page has been cleared with `\dfchapterclearpage`.



```
flowfram/chaphead/after
```

The `flowfram/chaphead/after` hook is used after the dynamic frame's content has been set. For example, you can use this hook to automatically append content to the dynamic frame with `\appenddynamiccontents`.



```
flowfram/chaphead/box/before
```

The `flowfram/chaphead/box/before` hook is used inside the heading box before the heading but after the known set of problematic commands have been adjusted. Since this hook

occurs within a `\parbox`, it will be scoped.

For example, this hook can be used to change the text colour of just the heading without affecting the colour of any content that is subsequently added to the frame:

```
\AddToHook{flowfram/chaphead/box/before}{\color
{blue}}
```

```
flowfram/chaphead/box/after
```

The `flowfram/chaphead/box/after` hook is used after the heading at the end of the box. Since this hook occurs within a `\parbox`, it will be scoped.

For example, this document defines a new dynamic frame called `chaphead` and uses it for chapter headings:

```
\newdynamicframe{0.38\textwidth}{\textheight}
{0.62\textwidth}{0pt}[chaphead]
\setdynamicframe*{chaphead}{evenx=0pt,clear}
\ChapterInDynamic*{chaphead}
```

Note that this provides a different horizontal position for even pages (specified with `evenx`) and the frame contents are automatically cleared on each new page (otherwise the chapter heading would show on every page).

The document class is `scrbook` so the KOMA-Script command that adds extra vertical space is redefined to do nothing (since the dynamic frame has its own custom dimensions):

```
\renewcommand\chapterheadstartvskip{}
```

and the chapter heading text is changed to blue:

```
\addtokomafont{chapter}{\color{blue}}
```

A mini-toc is also added to the same frame (see §6.2):

```
\appenddfminitoc*{chaphead}
```

I then defined a custom command to add a summary after the chapter heading:

```
\newcommand{\chapdesc}[1]{%
  \appenddynamiccontents*
  {chaphead}{\par \normalfont \emph{#1}}}%
}
```

For example, this chapter starts with:

```
\chapter{Defining New Frames}\label
{sec:newframes}

\chapdesc
{This chapter describes how to define new frames...}
```

Modern classes, such as memoir and the KOMA-Script classes provide ways of adjusting the style of chapter headings. These can be adjusted, as in the example above. However, if you are using the standard book or report class, flowfram will adjust the definitions to make

it easier to change the style.



The following commands are only provided if `\@makechapterhead` matches the definition provided by `book` or `report`.



`\ffchapterpreheadskip`

only if book or report class

Vertical space before the chapter heading. The default expansion is `\vspace*{50pt}` but this command is set to `\relax` in the `flowfram/chaphead/box/before` hook as leading vertical space is generally redundant at the start of a dynamic frame that has been specifically dedicated to holding the chapter heading.



`\ffchapterpostheadskip`

only if book or report class

Vertical space after the chapter heading. The default expansion is `\vspace*{40pt}`.



`\ffchapterheadstyle`

only if book or report class

The paragraph style for the chapter heading. The default definition sets `\parindent` to zero and sets ragged right formatting.



`\ffchapterdefaultfont`

only if book or report class

The default font declarations for the chapter heading. This can then be overridden by the following two commands (which both have an argument, unlike `\ffchapterdefaultfont`). The default definition is `\normalfont \bfseries`.

`\ffchaptertitlefont{text}`

only if book or report class

The font command for the chapter title (for both numbered and unnumbered chapters).

`\ffchapternamenumfont{text}`

only if book or report class

The font command for the chapter name and number (only applicable with numbered chapters). Note that the definition should scope any declarations otherwise they will also be applied to the chapter title.

`\ffchapternamenum{name}{number}`

only if book or report class

Typesets the chapter name (`\chaptername` or `\appendixname`) and number. The default definition expands to `name number`.

`\ffchapterpostnamenum`

only if book or report class

The separator between the chapter number and the title. The default definition inserts a paragraph break and vertical space.

2.4.2. Putting Headers and Footers in a Dynamic Frame

Page headers and footers can be turned into dynamic frames using:

```
\makedfheaderfooter
```

preamble only

This command will create two dynamic frames with special labels `header` and `footer`. You can then move or resize these using `\setdynamicframe` (see §2.4.4). Additionally, the page style will be set to `ffheadings`.

If you use FlowframTk (at least v0.8.8), you can additionally have different header and footer frames for even pages. These should be assigned the special labels `evenheader` and `evenfooter` with the page list set to “Even”. The dynamic frames for odd pages should be assigned the special labels `header` and `footer` with the page list set to “Odd”. This may be done via the Flow Frame Wizard (see the FlowframTk documentation for further details.)

Below, header frame and footer frame refer to the dynamic frames with the special labels `header` and `footer`, but also (if applicable) to the `evenheader` and `evenfooter` frames created with FlowframTk.

You can't simply create dynamic frames with `\newdynamicframe` with these special labels for this behaviour to work. You need to use the applicable command or application function. The frame content needs to be set to the appropriate code to ensure that it reflects the current page style. It's important not to use the `clear=true` setting or otherwise clear the content of these frames as this function would then be lost.

The `flowfram` package provides page styles that are customised for header and footer frames, which are listed below. Remember that you can set the frame style with the `style` setting, but you may prefer to modify the helper commands instead (which may counteract the `style` setting):

```
\dfOddFooterStyle{<text>}
```

This command is used to format the footer for odd pages, where applicable. The default centres `<text>` within the frame.

```
\dfEvenFooterStyle{<text>}
```

This command is used to format the footer for even pages, where applicable. The default centres `<text>` within the frame.

```
\dfOddHeaderStyle{<text>}
```

This command is used to format the header for odd pages, where applicable. The default places `<text>` flush right to the edge of the frame.

```
\dfEvenHeaderStyle{<text>}
```

This command is used to format the header for even pages, where applicable. The default places `<text>` flush left to the edge of the frame.

```
\flowframchapterheader{<text>}
```

This command is only defined if `\chapter` is defined and picks up the `dynamic-page-style-header-font` and `dynamic-header-case` settings.

`\flowframsectionheader{text}`

The definition of this command depends on whether or not `\chapter` is defined. If it isn't defined, the `dynamic-page-style-header-font` and `dynamic-header-case` settings will apply. If `\chapter` is defined, the `dynamic-page-style-subheader-font` and `dynamic-subheader-case` settings will apply.

`\flowframheadersep`

initial: varies

The separator used between the chapter or section number and the title (where a number is shown). If `\chapter` is defined, this is initialised to `. \` (period followed by a space) otherwise it is initialised to `\quad`.

`\flowframheaderchapprefix`

initial: varies

The prefix inserted before the chapter number. If `\chapter` is defined, the initial definition is `\@chapapp\` (`\chaptername` or `\appendixname` followed by a space) otherwise the initial definition is empty.

`fempty`

The default behaviour of the `fempty` page style clears the standard header and footer commands (`\@oddhead`, `\@evenhead`, `\@oddfoot` and `\@evenfoot`), as per the `empty` style, but also hides the special header and footer frames. This action may be changed with the `dynamic-empty-page-style` setting.

For example, suppose you have created fancy header and footer frames with a background and border. It may look strange to have these frames showing with empty content, so the default setting hides them as well. However, if you still want the frames to show, then you

would need to change the `dynamic-empty-page-style` option to a setting that doesn't hide them, such as `dynamic-empty-page-style=empty`.

`ffplain`

The default behaviour of the `ffplain` style is to have an empty header with `\thepage` centred in the footer. More precisely, this style sets `\@oddfoot` to:

```
\dfOddFooterStyle{\thepage}
```

and sets `\@evenfoot` to:

```
\dfEvenFooterStyle{\thepage}
```

Both `\@oddhead` and `\@evenhead` are set to `empty`. Additionally, if `ffempty` is set to hide the special header and footer frames, the `ffplain` style will ensure that `hide` and `hidethis` are set to `false` to counteract any previous instance of `ffempty`.

The `ffheadings` and `ffmyheadings` don't replicate the style of the standard `headings` and `myheadings` styles. Instead, the page number is always placed in the footer frame. If you want standard page headers and footers, there's no point switching to dynamic header and footer frames. Any minor stylist changes can be made using packages or document classes that provide support for flexible page styles.

`ffheadings`

The default behaviour of the `ffheadings` style depends on whether or not `\chapter` is defined. Note that the page number is still placed in the footer frame, as per the `ffplain` style. The right and left marks are placed in the applicable header frame.

This style sets \@oddfoot to

```
\dfOddFooterStyle{\thepage}
```

\@evenfoot to:

```
\dfEvenFooterStyle{\thepage}
```

\@oddhead to:

```
\dfOddHeaderStyle{\rightmark}
```

and \@evenhead to:

```
\dfOddHeaderStyle{\leftmark}
```

If `\chapter` is defined, `\chaptermark` is redefined to encapsulate the mark with `\flowframchapterheader` and `\sectionmark` is redefined to encapsulate the mark with `\flowframsectionheader`.

If `\chapter` is not defined, `\sectionmark` is redefined to encapsulate the mark with `\flowframsectionheader` and `\subsectionmark` is redefined to encapsulate the mark with `\flowframsubsectionheader`.

In either case, if `ffempty` is set to hide the special header and footer frames, the `ffheadings` style will ensure that `hide` and `hidethis` are set to `false` to counteract any previous instance of `ffempty`.

`ffmyheadings`

The `ffmyheadings` style is similar to the `ffheadings` style except that it sets the applicable mark commands to discard their argument. So, if `\chapter` is defined the `\chaptermark` and `\sectionmark` will be redefined to do nothing, otherwise `\sectionmark`

and `\subsectionmark` will be redefined to do nothing.



If the `dynamic-page-style=adjust` setting is on, `\makedfheaderfooter` will redefine the standard page styles (`empty`, `plain`, `headings` and `myheadings`) to the analogous `ffempty`, `ffplain`, `ffheadings` or `ffmyheadings` style.

2.4.3. Continued Text

As with static frames, in the body of `dynamiccontents` or `dynamiccontents*` or within the text of `\setdynamiccontents`, you can move onto another dynamic frame using:

```
\continueonframe [⟨text⟩] {⟨ID⟩}
```


to simulate text flowing from one dynamic frame to another. This command must not be hidden inside the definition of another command.



The `\continueonframe` command forces a break in the text whilst at the same time trying to justify it, so overly large space may occur.

In this case, if `\continueonframe` occurs within `dynamiccontents*`, `⟨ID⟩` refers to the IDL of the other dynamic frame, otherwise it refers to the IDN of the other dynamic frame. It's not possible to continue onto a different type of frame.

For example, suppose I have defined two dynamic frames labelled `frame1` (IDN 1) and `frame2` (IDN 2), then:




```
\begin{dynamiccontents*}{frame1}
Some text in the first frame. (Let's
assume this frame is somewhere on the
left half of the page.)
\continueonframe[Continued on the right]{frame2}
This is some text in the second frame. (Let's
assume this frame is somewhere on the
right half of the same page.)
\end{dynamiccontents*}
```

is essentially the same as:


```
\begin{dynamiccontents*}{frame1}
Some text in the first frame. (Let's
assume this frame is somewhere on the
left half of the page.)
\ffcontinuedtextlayout{Continued on the right}
\end{dynamiccontents*}
\begin{dynamiccontents*}{frame2}
\ffdynamicpostcontinued{1}{2}
This is some text in the second frame. (Let's
assume this frame is somewhere on the
right half of the same page.)
\end{dynamiccontents*}
```

When `\continueonframe` is used with dynamic frames it has analogous commands to those used with static frames. If the optional *⟨text⟩* is omitted, the default is obtained with:



```
\ffdefaultdynamiccontinuetext{⟨IDN1⟩}{⟨IDN2⟩}
      initial: \ffdefaultcontinuetext
```

This is like `\ffdefaultstaticcontinuetext` where the first argument is the IDN of the previous dynamic frame and the second argument is the IDN of the continuation dynamic frame. The default definition ignores its arguments and simply expands to `\ffdefaultcontinuetext`.



```
\ffdynamicpostcontinued{⟨IDN1⟩}{⟨IDN2⟩}
      initial: \ffdefaultpostcontinued
```

This is like `\ffstaticpostcontinued` where the first argument is the IDN of the previous dynamic frame and the second argument is the IDN of the continuation dynamic frame. The default definition ignores its arguments and simply expands to `\ffdefaultpostcontinued`.

2.4.4. Important Notes

- Verbatim text can't be used in a dynamic frame. This includes the body of the `dynamiccontents` and `dynamiccontents*` environments.
- `\continueonframe` can't be used in the argument of any of the commands that append to the contents of a dynamic frame, such as `\appenddynamiccontents`.
- `\continueonframe` causes a change in scope so any local changes made before the command won't still be in effect after it.
- Dynamic frames are painted on the page after all the static and flow frames. If the location of a dynamic frame overlaps the location of any static or flow frames, the contents of the dynamic frame will obscure the contents of the overlapping frames.

Once you have defined the flow frames, static frames and dynamic frames, their attributes can be changed. The three types of frame mostly have the same set of attributes, but some are specific to a certain type.

Attributes are global. Changes usually come into effect during the output routine. Dimension and text colour are best set in the preamble, especially for flow frames and static frames.

Flow frames attributes are modified using:

```
\setflowframe{<ID-list>}{<key=value list>} modifier: *
```

Alternatively, you can set the same attributes for all defined flow frames with:

```
\setallflowframes{<key=value list>}
```

Static frames attributes are modified using:

```
\setstaticframe{<ID-list>}{<key=value list>} modifier: *
```

Alternatively, you can set the same attributes for all defined static frames with:

```
\setallstaticframes{<key=value list>}
```

Dynamic frames attributes are modified using:

3. Modifying Frame Attributes

- 3.1. Set Frame Options 70
 - 3.1.1. Identification and Scope 71
 - 3.1.2. Content Attributes 75
 - 3.1.3. Layout Attributes 78
 - 3.1.4. Appearance 85
 - 3.1.5. HTML 89
- 3.2. Non-Rectangular Frames 91
- 3.3. Switching Frames On and Off On-The-Fly 94

This chapter describes how to modify frame attributes, such as the size and location.

```
\setdynamicframe{⟨ID-list⟩}{⟨key=value list⟩}
```

modifier: *

Alternatively, you can set the same attributes for all defined dynamic frames with:

```
\setalldynamicframes{⟨key=value list⟩}
```

In each of the above `\set⟨type⟩frame` commands, if the starred version is used then `⟨ID-list⟩` should be a comma-separated list of IDLs that identify the frames for which the attributes need to be applied. Note that you can't use ranges or the keywords described below with the starred versions.

In the case of the unstarred version the `⟨ID-list⟩` can either be a list or range of IDNs that identify the required frames or one of the keywords `all`, `odd` or `even`. The `all` keyword is essentially equivalent to using the corresponding `\setall⟨type⟩frames`. The `odd` keyword indicates that all frames with an odd IDN should be set. The `even` keyword indicates that all frames with an even IDN should be set.

The `all`, `odd` and `even` keywords used to identify frames should not be confused with the `all`, `odd` and `even` page list keywords.

The `⟨key=value list⟩` argument is a comma-separated list of `⟨key⟩=⟨value⟩` settings. **Make sure that you group the `⟨value⟩` if it contains one or more commas or equal signs.** Available options are listed in §3.1.

3.1. Set Frame Options

Some attributes are shared by all types of frame but some are only available for a particular type of frame.

3.1.1. Identification and Scope

`label=⟨IDL⟩`

The frame's IDL can be assigned with the `label` option. This may be needed when a frame is created by a helper command, such as `\Ncolum` (see §4.3). In general, it's best to set the IDL when the frame is defined. (If you do not specify a label when you first define a frame it will be given a label identical to its IDN.)

`pages=⟨page-list⟩ | ⟨keyword⟩`

The frame's page list is set when the frame is defined. The default is `all`. The `pages` option may be used to change the page list. The value may be either `⟨page-list⟩` or `⟨keyword⟩`.

Changing the page list mid-document can cause unpredictable results. You may lose text if the frame has already had content added to it on the current page. See §3.3 for switching frames on and off mid-document.

Allowed values for `⟨keyword⟩`:

`none`

The frame should not be displayed on any page.

`all`

The frame should be displayed on all pages, unless exceptions apply.

`even`

The frame should only be displayed on even pages if the document is two-sided, unless exceptions apply.

odd

The frame should only be displayed on odd pages if the document is two-sided, unless exceptions apply.

Otherwise the value should be *<page-list>*, a list or range of numbers identifying on which page or pages the frame should be shown. Ranges may be closed, such as 3–9 (which indicates pages 3 to 9 inclusive), or open-ended, such as <3 (which indicates any page less than 3) or >9 (which indicates any page greater than 9). The *<page-list>* may be a single range or a comma-separated list of individual pages or ranges, such as <3, 5–12, >20.



Each number in the list must be a plain positive integer (1, 2, etc) not a formatted number.

The page list may also be set using:



```
\flowsetpagelist{<IDN>}{<page-list>|<keyword>}
```

This sets the page list for a specific flow frame identified by its IDN.



```
\staticsetpagelist{<IDN>}{<page-list>|<keyword>}
```

This sets the page list for a specific static frame identified by its IDN.



```
\dynamicsetpagelist{<IDN>}{<page-list>|<keyword>}
```

This sets the page list for a specific dynamic frame identified by its IDN.



There are no starred versions for the `\<type>setpagelist` commands and `\<IDN>` must be a number that identifies a specific frame.

The numbers refer to the counter identified by the `pages` package option. With `pages=relative`, the numbers refer to the value of the page counter (not the formatted text obtained with `\thepage`). This can be ambiguous if the page counter is reset in the document. With `pages=absolute`, the numbers refer to the value of the absolute-page counter, which should not be reset in the document and is incremented by the output routine whenever a page is shipped out.



With `pages=relative`, not only can you have multiple pages with the same numeric value (for example, page i and page ii) but there's also no way of determining whether or not the next page will have the number reset. When the `flowfram` code in the output routine looks ahead to determine which flow frame it needs to switch to, it will assume that the value of the next page is one more than the value of the current page. For example, if the current page is “iv” (4) then the next page is assumed to have the value 5 and `flowfram` will select the next flow frame on that basis. If it turns out that the page counter is then reset so that `\thepage` is now 1, if that's outside the range of the selected flow frame then you may lose text.



`excludepages=<list>`

Certain pages can be excluded from a frame's page list. For example, if a frame's page list is set to `all` but it has `excludepages={2, 9}` then the frame will be shown on all pages except for page 2 and page 9. Note that in this case the value is just a list of numbers. See also §3.3 for switching frames on and off mid-document.

It's also possible to set the exclusion list the following commands:

```
\flowsetexclusion{⟨IDN⟩}{⟨list⟩}
```

Sets the exclusion list for a flow frame.

```
\flowaddexclusion{⟨IDN⟩}{⟨list⟩}
```

Appends to the existing exclusion list for a flow frame.

```
\staticsetexclusion{⟨IDN⟩}{⟨list⟩}
```

Sets the exclusion list for a static frame.

```
\staticaddexclusion{⟨IDN⟩}{⟨list⟩}
```

Appends to the existing exclusion list for a static frame.

```
\dynamicsetexclusion{⟨IDN⟩}{⟨list⟩}
```

Sets the exclusion list for a dynamic frame.

```
\dynamicaddexclusion{⟨IDN⟩}{⟨list⟩}
```

Appends to the existing exclusion list for a dynamic frame.

There are no starred versions for these commands and the *⟨IDN⟩* argument should be a single number.

`hide=<boolean>`*default: **true**; initial: **false***

A frame can also be omitted if the boolean `hide` option is set. If true, this overrides the page list and omits the frame for all pages.

`hidethis=<boolean>`*default: **true**; initial: **false***

A frame can also be omitted if the boolean `hidethis` option is set. If true, this overrides the page list and omits the frame for this pages. The value will be reset when the current page is shipped out.

3.1.2. Content Attributes

`clear=<boolean>`*default: **true**; initial: **false**
static & dynamic only*

This boolean option is only available for static frame and dynamic frame. If true, the frame contents will be cleared on each new page.

If you set `clear=true` for a special dynamic frame, such as `header` or `footer`, they will lose their special function.

In this document, I have used `\ChapterInDynamic` to put the chapter titles in a dynamic frame called `chaphead`. This isn't a special frame, but the contents are reset every time `\chapter` is used. I've also used `\appenddfminitoc` which then appends the chapter's mini-toc to that frame. And finally, I have a custom command that appends a brief summary. For example, this chapter is started with:

```
\chapter{Modifying Frame Attributes}\label
{sec:modattr}
\chapdesc
{This chapter describes how to modify frame attributes,
such as the size and location.}
```

However, I only want this content visible on the first page of the chapter, so I've set the `clear` option for the `chaphead` frame. This ensures that the content is cleared whenever a new page starts.

I've also used `\makedfheaderfooter` and `\makethumbtabs`. This automatically defines a set of special dynamic frames. In this case, the `clear` option should not be set as clearing the content will remove the code that ensures the header, footer and thumbtab show the correct information.

```
parindent=<dim expr>
```

```
initial: \sdfparindent
```

This option is only available for static frames and dynamic frames. The value should be a dimension (either explicit, such as `5pt`, or a variable, such as `\sdfparindent`, or an expression, such as `1em + 0.1\linewidth`). The default is `\sdfparindent`.

The dimension won't be evaluated until the contents of the frame are typeset. For static frames this is when the frame content is set, and for dynamic frames this is every time the frame is placed on the page by the output routine.

```
style=<value>
```

```
initial: none
```

This option is only available for dynamic frames. The value may be the keyword `none` (equivalent to `@firstofone`) or the name of a declaration or a text-block command (without the leading backslash).

For example:

```
\setdynamicframe{1}{style={emph}}
```

The above will encapsulate the contents of the dynamic frame identified by IDN 1 with `\emph`.

Bear in mind that text-block commands such as `\emph` and `\textbf` introduce grouping which may result in subtle spacing issues. If this is a problem, try using the analogous declaration instead. For example:

```
\setdynamicframe{1}{style={em}}
```

The frame content is already scoped and no extra grouping is introduced with this method for standard rectangular frames. (Extra grouping is added for shaped frames.)

Example 1 provided a custom command:

```
\newcommand{\Hugebf}{\Huge\bfseries}
```

and the `sidepanel` dynamic frame had `style=Hugebf` set. This command could have been defined as:

```
\newcommand{\Hugebf}[1]{\textbf{\Huge #1}}
```

but if you try this out you would find that the interline spacing is much smaller. This is because the paragraph doesn't end until after the styling command so the line skip for `\Huge` is wrong. The text is `Huge` but the line spacing is normal size.



The FlowframTk dialog windows used to specify frame attributes are different: the “Style” field should be left blank for no styling or may be a command name like `emph` (as for `style`) but may also be a list of declarations (with optionally a final text-block command). When FlowframTk exports the information, if the “Style” field contains one or more backslashes it will use commands provided by `flowframtkutils` to define a custom command that can then be used in the `style` option.

If you are not using FlowframTk and you need more than one command to apply the style then you will need to define your own custom command and use that instead (as in Example 1).



`shape=⟨value⟩`

initial: `\relax`

This key is only available for static frames and dynamic frames and sets the paragraph shape for the frame contents. See §3.2 for further details.



`valign=⟨value⟩`

initial: `varies`

This key is only available for static frames and dynamic frames and sets the vertical alignment of the content within the frame. The default is `c` for static frames and `t` for dynamic frames.

3.1.3. Layout Attributes



`margin=⟨value⟩`

initial: `right`

This option is only available for flow frames and indicates on which side of the flow frame the margin should be placed. The value may be one of the keywords: `inner`, `outer`,

left or right.

For two-sided documents, `inner` places the margin on the left for odd pages and on the right for even pages, and `outer` places the margin on the right for odd pages and on the left for even pages.

For one-sided documents, `inner` is the same as `left` (place to the left of the frame) and `outer` is the same as `right` (place to the right of the frame).

`offset=<dimension> | compute`

initial: `compute`

Sets the frame's offset to take the border into account. The value may be a dimension or the keyword `compute`, which will compute the offset if the frame has a known border (`\fbox`, `\ovalbox`, `\Ovalbox` and `\doublebox`). If the border is unknown then the offset for `\fbox` will be used.

If the frame has a border set and it takes up extra space (caused by the padding between the border and the text and the size of the frame) then this attribute needs to be set to shift the frame so that the bottom left corner of the text area within the frame is at the designated x and y -coordinates.

This setting is not required with `FlowframTk` as it calculates the offset based on the supplied inner padding.

`width=<dimension>`

Set the width of the frame to the given `<dimension>`. This is available for all types of frame but be careful not to change this value after any content has been added to the frame.

The width can be obtained for a flow frame with:



```
\flowframewidth{⟨IDN⟩}
```

where $\langle IDN \rangle$ is the flow frame's IDN. The width can be obtained for a static frame with:



```
\staticframewidth{⟨IDN⟩}
```

where $\langle IDN \rangle$ is the static frame's IDN. The width can be obtained for a dynamic frame with:



```
\dynamicframewidth{⟨IDN⟩}
```

where $\langle IDN \rangle$ is the dynamic frame's IDN. In each case, the command simply expands to the dimension.



```
height=⟨dimension⟩
```

Set the height of the frame to the given $\langle dimension \rangle$. This is available for all types of frame but be careful not to change this value after any content has been added to the frame.

The height can be obtained for a flow frame with:



```
\flowframeheight{⟨IDN⟩}
```

where $\langle IDN \rangle$ is the flow frame's IDN. The height can be obtained for a static frame with:



```
\staticframeheight{⟨IDN⟩}
```

where $\langle IDN \rangle$ is the static frame's IDN. The height can be obtained for a dynamic frame with:

```
\dynamicframeheight{⟨IDN⟩}
```

where $\langle IDN \rangle$ is the dynamic frame's IDN. In each case, the command simply expands to the dimension.

```
x=⟨dimension⟩
```

Set the x -coordinate of the frame for all pages on which it's defined. This is available for all types of frame. Note that $x=\langle position \rangle$ is equivalent to setting both `oddx=⟨position⟩` and `evenx=⟨position⟩`.

```
y=⟨dimension⟩
```

Set the y -coordinate of the frame for all pages on which it's defined. This is available for all types of frame. Note that $y=\langle position \rangle$ is equivalent to setting both `oddy=⟨position⟩` and `eveny=⟨position⟩`.

```
evenx=⟨dimension⟩
```

Set the frame's x -coordinate for all even pages on which it's defined (only applicable if the document is two-sided). For example:

```
\setflowframe*{main}{evenx={0.4\typeblockwidth}}
\setdynamicframe*{chaphead}{evenx=0pt}
```

This changes the horizontal position of the flow frame labelled `main` and the dynamic frame labelled `chaphead` on even pages (provided the document has the two-sided setting on).

The even-page x -coordinate can be obtained for a flow frame with:

```
\flowframeevenx{⟨IDN⟩}
```

where $\langle IDN \rangle$ is the flow frame's IDN. The even-page x -coordinate can be obtained for a static frame with:

```
\staticframeevenx{⟨IDN⟩}
```

where $\langle IDN \rangle$ is the static frame's IDN. The even-page x -coordinate can be obtained for a dynamic frame with:

```
\dynamicframeevenx{⟨IDN⟩}
```

where $\langle IDN \rangle$ is the dynamic frame's IDN. In each case, the command simply expands to the dimension.

```
eveny=⟨dimension⟩
```

Set the frame's y -coordinate for all even pages on which it's defined (only applicable if the document is two-sided).

The even-page y co-ordinate can be obtained for a flow frame with:

```
\flowframeeveny{⟨IDN⟩}
```

where $\langle IDN \rangle$ is the flow frame's IDN. The even-page y co-ordinate can be obtained for a static frame with:

```
\staticframeeveny{⟨IDN⟩}
```

where $\langle IDN \rangle$ is the static frame's IDN. The even-page y co-ordinate can be obtained for a dynamic frame with:

```
\dynamicframeeveny{⟨IDN⟩}
```

where $\langle IDN \rangle$ is the dynamic frame's IDN. In each case, the command simply expands to the dimension.

```
oddx=⟨dimension⟩
```

Set the frame's x -coordinate for all odd pages (or all pages for one-sided documents) on which it's defined.

The odd-page x -coordinate can be obtained for a flow frame with:

```
\flowframex{⟨IDN⟩}
```

where $\langle IDN \rangle$ is the flow frame's IDN. The odd-page x -coordinate can be obtained for a static frame with:

```
\staticframex{⟨IDN⟩}
```

where $\langle IDN \rangle$ is the static frame's IDN. The odd-page x -coordinate can be obtained for a dynamic frame with:

```
\dynamicframex{⟨IDN⟩}
```

where $\langle IDN \rangle$ is the dynamic frame's IDN. In each case, the command simply expands to the dimension.

`oddy= $\langle dimension \rangle$`

Set the frame's y -coordinate for all odd pages (or all pages for one-sided documents) on which it's defined.

The odd-page y -coordinate can be obtained for a flow frame with:

`\flowframey{ $\langle IDN \rangle$ }`

where $\langle IDN \rangle$ is the flow frame's IDN. The odd-page y -coordinate can be obtained for a static frame with:

`\staticframey{ $\langle IDN \rangle$ }`

where $\langle IDN \rangle$ is the static frame's IDN. The odd-page y -coordinate can be obtained for a dynamic frame with:

`\dynamicframey{ $\langle IDN \rangle$ }`


where $\langle IDN \rangle$ is the dynamic frame's IDN. In each case, the command simply expands to the dimension.

There are also commands available to swap the odd and even co-ordinates:

`\ffswapoddeven{ $\langle ID-list \rangle$ }`

*modifier: **


This swaps the odd and even co-ordinates for each flow frame in $\langle ID-list \rangle$. (The $\langle ID-list \rangle$ is as for `\setflowframe`.)



```
\sfswapoddeven{⟨ID-list⟩}
```

*modifier: **

This swaps the odd and even co-ordinates for each static frame in $\langle ID\text{-}list \rangle$. (The $\langle ID\text{-}list \rangle$ is as for `\setstaticframe`.)




```
\dfswapoddeven{⟨ID-list⟩}
```

*modifier: **

This swaps the odd and even co-ordinates for each dynamic frame in $\langle ID\text{-}list \rangle$. (The $\langle ID\text{-}list \rangle$ is as for `\setdynamicframe`.)


3.1.4. Appearance



```
angle=⟨angle⟩
```

initial: 0

Rotates the frame by $\langle angle \rangle$ degrees. Note the bounding boxes are not rotated in draft mode.



```
border=⟨value⟩
```

*default: **plain**; initial: **false***

Sets the frame's border. The $\langle value \rangle$ may be the keyword `plain` (use a plain border, equivalent to `border=fbox`), `false` (no border) or may be the control sequence name (without the leading backslash) of a frame making command. If you set a border for a frame, you may also need to specify the `offset` if the default computation is incorrect. The rule width for the plain border is governed by `\flowframerule` (see §7.2).

The `fancybox` package provides the commands `\shadowbox`, `\doublebox`, `\ovalbox` and `\Ovalbox`, which may all be used as a border. For example, `border=ovalbox`. Remember to load the `fancybox` package if you want to use any of these commands as a border.

For example, to make the first static frame have an oval border:

```
\setstaticframe{1}{border=ovalbox}
```

Or you can define your own border, for example with `\fcolorbox`:

```
\newcommand{\greenyellowbox}[1]{\fcolorbox{green}{yellow}{#1}}
\setstaticframe{1}{border=greenyellowbox}
```

In this case, the border incorporates colour so the `bordercolor` and `backcolor` settings should be none.

If you use FlowframTk to create the frames, remember to set the “border as shown” option if you want the shape to be the border. FlowframTk will define the border command and deal with the offset, border colour, text colour and background colour.

```
bordercolor = [ <colour-space> ] { <colour-specs> }
```

initial: none

Sets the colour of the border. The value may be the keyword `none` (no colour change) or the colour specifications as suitable for `\color`.

This option will have no effect with borders created by FlowframTk as the colour specifications will be included in the custom border command.

`border-color`*alias:* `bordercolor`

Synonym for `bordercolor`.

`bordercolour`*alias:* `bordercolor`

Synonym for `bordercolor`.

`border-colour`*alias:* `bordercolor`

Synonym for `bordercolor`.

`background= [<colour-space>] { <colour-specs> }`*initial:* **none**

Sets the colour of the frame's background. The value may be the keyword `none` (no colour change) or the colour specifications as suitable for `\color`.


If you are using `FlowframTk`, set the shape's fill colour instead of using this option or you may end up with blank areas in the border padding.

`back-color`*alias:* `backcolor`

Synonym for `backcolor`.


`backcolour`*alias:* `backcolor`

Synonym for `backcolor`.

back-colour


alias: backcolor

Synonym for backcolor.


textcolor= [*<colour-space>*] { *<colour-specs>* }

initial: none

Sets the colour of the frame's text. The value may be the keyword `none` (no colour change) or the colour specifications as suitable for `\color`.



It's best to keep to the default document colour for all flow frames otherwise inconsistencies can occur when paragraphs span across frames and also the footnotes will now be in the document colour. (This has changed in v2.0 as it requires too much meddling with the output routine to alter the footnote colour.) The default document colour can be set by using `\color [<color-space>] { <colour-specs> }` in the preamble.

text-color


alias: textcolor

Synonym for textcolor.

textcolour

alias: textcolor

Synonym for textcolor.

text-colour

alias: textcolor

Synonym for textcolor.

3.1.5. HTML

The need to know where page breaks occur can make it hard for a \LaTeX to HTML parser that doesn't use a \LaTeX engine to generate HTML output. The arbitrary location of frames can make it hard to support the `flowfram` package. As from version 2.0, there is now an option specifically to help support parsers that don't have access to the output routine.

```
html={\langle key=value list \rangle}
```

static and dynamic only

When the document is processed by \LaTeX , this option simply writes information to the `aux` file. The `aux` command depends on whether or not the `html` option was in the preamble or in the document environment.

```
\flowfram@preamble@htmlopts{\langle n \rangle}{\langle key=value  
list \rangle}{\langle type \rangle}{\langle IDN \rangle}{\langle page \rangle}{\langle absolute-page \rangle}
```

This command will be written to the `aux` file if the `html` option was set in the preamble.

```
\flowfram@doc@htmlopts{\langle n \rangle}{\langle key=value  
list \rangle}{\langle type \rangle}{\langle IDN \rangle}{\langle page \rangle}{\langle absolute-page \rangle}
```

This command will be written to the `aux` file if the `html` option was set in the document environment.

Both commands have the same syntax. The first argument $\langle n \rangle$ is a number that starts at 1 and is incremented every time that the `html` option is applied. The $\langle key=value list \rangle$ option is the value of the `html` option. The $\langle type \rangle$ is the frame type, which will either be static or dynamic. The $\langle IDN \rangle$ argument is the frame's IDN. The final two arguments, $\langle page \rangle$ and $\langle absolute-page \rangle$, are the values of `\thepage` and `\theabsolutepage`.

It's up to the \LaTeX to HTML parser to choose what options in $\langle key=value list \rangle$ to

implement. The following are options recognised by the T_EX Parser Library, which is used by the system that creates the HTML helpset files for some of my Java GUI applications, including FlowframTk:

`show=⟨boolean⟩`

default: **true**; initial: **false**

This boolean option indicates that the frame contents should be shown at this point. If this value is true, then the following options govern how the content is shown.

`div=⟨boolean⟩`

default: **true**; initial: **true**

If true, the content should be encapsulated in a `div` element.

`style=⟨css⟩`

If `div=true`, then the `style` attribute should be set to `⟨css⟩`.

`class=⟨css-class⟩`

If `div=true`, then the `class` attribute should be set to `⟨css-class⟩`.


`image=⟨boolean⟩`

default: **true**; initial: **false**

If true, the content should be converted to an image. This typically indicates that the content is too complicated to convert to HTML.

`mime-type=⟨type⟩`

If `image=true`, the image should have the given MIME type.




```
alt=\text
```

If `image=true`, the image's `alt` attribute should be set to `\text`.

3.2. Non-Rectangular Frames

As from version 1.03, it is now possible to specify non-rectangular static or dynamic frames (but not flow frames). Note that the bounding box will still appear as a rectangle despite the frame's shape setting. You may use either T_EX's `\parshape` command, or the `\shapepar`/`\Shapepar` commands defined in Donald Arseneau's `shapepar` package (if using `\shapepar` or `\Shapepar`, remember to include the `shapepar` package.)



FlowframTk can compute the parameters of `\parshape` or `\shapepar`/`\Shapepar` from a shape (limitations may apply). You can either export the parameters to a T_EX file that can simply be `\input` at the start of a paragraph or, if you are creating a static or dynamic frame you can set the “Shape” selector to “Parshape” or “Shapepar” as applicable. Use the “Configure T_EX Settings” dialog to specify whether you want `\shapepar` or `\Shapepar` for the “Shapepar” setting. See the FlowframTk manual for further details.

The `\shapepar` or `\Shapepar` commands provide greater flexibility in the type of shape that can be used. However, be aware of the advice given in the `shapepar` documentation.

`\parshape`

With `\parshape` you can not have cut-outs in the middle, top or bottom of a frame, however it is possible to have cut-outs in the left or right side of the frame. When used with the `shape` key for static or dynamic frames, the effects of `\par` and the

sectioning commands (`\section` and below) are modified to allow the paragraph shape to extend beyond a single paragraph, and to allow sectioning commands (but not `\chapter` or `\part`).

`\shapepar/\Shapepar`

With `\shapepar` or `\Shapepar` you may have cut-outs, but you may not have any sectioning commands, paragraph breaks, vertical spacing or mathematics. You can simulate a paragraph break using `\FLFSimpar`, but this is not recommended. The size of the shape depends on the amount of text, so the shape will expand or contract as you add or delete text. In general, `\Shapepar` is better suited for use as a frame shape than `\shapepar`. See the `shapepar` documentation for more details of these commands.

To restore a static or dynamic frame to its default rectangular setting, use `shape\relax`. For those unfamiliar with TeX's `\parshape` command, the syntax is:

```
\parshape=<n> <i1> <l1> <i2> <l2> ... <in> <ln>
```

where $\langle n \rangle$ is the number of $(\langle i_j \rangle \langle l_j \rangle)$ pairs and $\langle i_j \rangle$ specifies the left indentation for the j th line and $\langle l_j \rangle$ specifies the length of the j th line.

For example, to create a zigzag shaped static frame (whose IDL is `shapedt`):

```
\setstaticframe*{shapedt}{shape={\parshape=20
0.6\linewidth 0.4\linewidth
0.5\linewidth 0.4\linewidth
0.4\linewidth 0.4\linewidth
0.3\linewidth 0.4\linewidth
0.2\linewidth 0.4\linewidth
0.1\linewidth 0.4\linewidth
0pt 0.4\linewidth 0.1\linewidth 0.4\linewidth
```

```

0.2\linewidth 0.4\linewidth
0.3\linewidth 0.4\linewidth
0.4\linewidth 0.4\linewidth
0.5\linewidth 0.4\linewidth
0.6\linewidth 0.4\linewidth
0.5\linewidth 0.4\linewidth
0.4\linewidth 0.4\linewidth
0.3\linewidth 0.4\linewidth
0.2\linewidth 0.4\linewidth
0.1\linewidth 0.4\linewidth
Opt 0.4\linewidth 0.1\linewidth 0.4\linewidth
}}
```

Previously it was possible to have paragraph-breaking content such as displayed maths or the verbatim environment in a shaped paragraph. Due to various underlying changes this is no longer possible. You will now need to insert the `\parshape` command in the appropriate places in the frame content instead of in the `shape` option.

The syntax for `\shapepar` and `\Shapepar` is more complicated, see the `shapepar` documentation for more details. In general:

```
\shapepar{<shape specs>}
```

The `shapepar` package has some predefined shapes, such as `\squareshape`, `\diamondshape`, `\heartshape` and `\nutshape`.

For example, to assign a heart shape to the static frame whose IDL is `shapedb`:

This is an example of a static frame with a non-rectangular shape. This zigzag shape was specified using the `shape` option in `\set-staticframe`. The `\parshape` command was used to set the shape. Using the `shape` key rather than explicitly using `\parshape` means that I can have a paragraph break whilst retaining the shape **but there are limitations**.

This example has a more complicated shape that can not be generated using TeX's `\parshape` command, so `\shapepar` was used instead. Note that this document must include the `shapepar` package in this instance, whereas no extra packages are required to use `\parshape`. No sectioning commands are allowed here. The shape will expand as more text is added to it.

♡

```
\setstaticframe*{shapedb}{shape={\shape-
par\heartshape}}
```

To reset the frame back to its original rectangular shape do:

```
\setstaticframe*{shapedb}{shape=\relax}
```

The `flowfram` package currently does not support any other paragraph shape making commands. Any other commands would have to be used explicitly within the contents of the frame.

3.3. Switching Frames On and Off On-The-Fly

Modifying the page list (or the page exclusion list) within the document environment is a risky business. This list must be up-to-date before the output routine looks for the next frame. To make this a little easier, as from version 1.14 there are commands that help you do this.

If you want to use these commands, it's best to use the package option `pages=absolute`.

The commands described in this section update the page lists (and possibly the exclusion list) *when the output routine is next used*. They are designed to switch frames on or off either on the next page or on the next odd page. You therefore need to take care where you place these commands. For example, if you have a two-sided document and you do:

```
\dynamicswitchonnextodd{1}
\mainmatter
\chapter{Introduction}
```

This will set the dynamic frame whose IDN is 1 to be visible for the first page of chapter 1. However, if you do

```
\mainmatter
\dynamicswitchonnextodd{1}
\chapter{Introduction}
```

This will have a different effect as `\mainmatter` issues a `\cleardoublepage` so the command to switch on the dynamic frame is on the same page as the start of chapter 1. This means that the dynamic frame won't appear until the following odd page (page 3).

These commands all have the same syntax with one argument that may be a comma-separated list. The starred version uses the IDLs and the unstarred version uses the IDNs.

```
\flowswitchonnext{⟨ID-list⟩} modifier: *
```

Switch on the listed flow frames from the following page onwards.

```
\flowswitchoffnext{⟨ID-list⟩} modifier: *
```

Switch off the listed flow frames from the following page onwards.

```
\flowswitchonnextodd{⟨ID-list⟩} modifier: *
```

Switch on the listed flow frames from the next odd page onwards.

```
\flowswitchoffnextodd{⟨ID-list⟩}
```

*modifier: **

Switch off the listed flow frames from the next odd page onwards.

```
\flowswitchonnextonly{⟨ID-list⟩}
```

*modifier: **

Switch on the listed flow frames just for the following page.

```
\flowswitchoffnextonly{⟨ID-list⟩}
```

*modifier: **

Switch off the listed flow frames just for the following page.

```
\flowswitchonnextoddonly{⟨ID-list⟩}
```

*modifier: **

Switch on the listed flow frames just for the next odd page.

```
\flowswitchoffnextoddonly{⟨ID-list⟩}
```

*modifier: **

Switch off the listed flow frames just for the next odd page.

```
\dynamicswitchonnext{⟨ID-list⟩}
```

*modifier: **

Switch on the listed dynamic frames from the following page onwards.

```
\dynamicswitchoffnext{⟨ID-list⟩}
```

*modifier: **

Switch off the listed dynamic frames from the following page onwards.

`\dynamicswitchonnextodd{⟨ID-list⟩}` *modifier: **

Switch on the listed dynamic frames from the next odd page onwards.

`\dynamicswitchoffnextodd{⟨ID-list⟩}` *modifier: **

Switch off the listed dynamic frames from the next odd page onwards.

`\dynamicswitchonnextonly{⟨ID-list⟩}` *modifier: **

Switch on the listed dynamic frames just for the following page.

`\dynamicswitchoffnextonly{⟨ID-list⟩}` *modifier: **

Switch off the listed dynamic frames just for the following page.

`\dynamicswitchonnextoddonly{⟨ID-list⟩}` *modifier: **

Switch on the listed dynamic frames just for the next odd page.

`\dynamicswitchoffnextoddonly{⟨ID-list⟩}` *modifier: **

Switch off the listed dynamic frames just for the next odd page.

`\staticswitchonnext{⟨ID-list⟩}` *modifier: **

Switch on the listed static frames from the following page onwards.

```
\staticswitchoffnext{⟨ID-list⟩}
```

*modifier: **



Switch off the listed static frames from the following page onwards.

```
\staticswitchonnextodd{⟨ID-list⟩}
```

*modifier: **



Switch on the listed static frames from the next odd page onwards.

```
\staticswitchoffnextodd{⟨ID-list⟩}
```

*modifier: **



Switch off the listed static frames from the next odd page onwards.

```
\staticswitchonnextonly{⟨ID-list⟩}
```

*modifier: **



Switch on the listed static frames just for the following page.

```
\staticswitchoffnextonly{⟨ID-list⟩}
```

*modifier: **



Switch off the listed static frames just for the following page.

```
\staticswitchonnextoddonly{⟨ID-list⟩}
```

*modifier: **



Switch on the listed static frames just for the next odd page.

```
\staticswitchoffnextoddonly{⟨ID-list⟩}
```

*modifier: **



Switch off the listed static frames just for the next odd page.

The `flowfram` package comes with a sample file `sample-pages.tex` that uses some of these commands.

This chapter describes some of the commands available that can be used to determine the locations and dimensions of frames. See the accompanying document `flowfram-code.pdf` for more details of these commands or for other commands not listed here.

4. Locations and Dimensions

4.1. Determining the Location of the Typeblock

As mentioned earlier, when you create new frames, you must specify their location relative to the typeblock, but what if you want to position a frame a set distance from the edge of the paper? The `flowfram` package provides the following commands that compute the distance from the typeblock to the paper boundary. Since odd and even pages may have a different offset if `\oddsidemargin` and `\evensidemargin` have different values, there are separate commands for horizontal measurements on odd and even pages.

```
\computeleftedgeodd{⟨dim var⟩}
```

Computes the position of the left edge of the page, relative to the left side of the typeblock, for odd pages, and stores the result in the dimension variable (length register) `⟨dim var⟩`.

```
\computeleftedgeeven{⟨dim var⟩}
```

Computes the position of the left edge of the page, relative to the left side of the typeblock, for even pages, and stores the result in the dimension variable (length register) `⟨dim var⟩`.

```
\computetopedge{⟨dim var⟩}
```

Computes the top edge of the page, relative to the bottom of the typeblock, and stores the result in the dimension variable (length register) `⟨dim var⟩`.

- 4.1. Determining the Location of the Typeblock 101
- 4.2. Determining the Dimensions and Locations of Frames 103
- 4.3. Relative Locations 103

This chapter describes some of the commands provided to determine the locations and dimensions of frames.



```
\computebottomedge{<dim var>}
```

Computes the bottom edge of the page, relative to the bottom of the typeblock, and stores the result in the dimension variable (length register) *<dim var>*.



```
\computerightedgeodd{<dim var>}
```

Computes the position of the right edge of the page, relative to the left side of the typeblock, for odd pages, and store the result in the dimension variable (length register) *<dim var>*.



```
\computerightedgeeven{<dim var>}
```

Computes the position of the right edge of the page, relative to the left side of the typeblock, for even pages, and store the result in the dimension variable (length register) *<dim var>*.

For example, if you want to create a frame whose bottom left corner is one inch from the left edge of the page and half an inch from the bottom edge of the page (this assumes odd and even pages have the same margins):



```
% define two new lengths to store the x and y coords
\newlength{\myX}
\newlength{\myY}
% compute the distance from typeblock to the paper edge
\computeleftedgeodd{\myX}
\computebottomedge{\myY}
% Add the absolute co-ordinates to get co-ordinates
% relative to the typeblock
\addtolength{\myX}{1in}
\addtolength{\myY}{0.5in}
```

4.2. Determining the Dimensions and Locations of Frames

It is possible to determine the dimensions and locations of a frame using one of the following commands. For each command, the starred version identifies the frame by its IDL and the unstarred version identifies it by its IDN. The results are stored in the length registers `\ffareax` (the x -coordinate), `\ffareay` (the y -coordinate), `\ffareawidth` (the frame's width) and `\ffareaheight` (the frame's height).

```
\getstaticbounds{⟨ID⟩}
```

*modifier: **

Gets the bounds for the static frame identified by `⟨ID⟩`.

```
\getflowbounds{⟨ID⟩}
```

*modifier: **

Gets the bounds for the flow frame identified by `⟨ID⟩`.

```
\getdynamicbounds{⟨ID⟩}
```

*modifier: **

Gets the bounds for the dynamic frame identified by `⟨ID⟩`.

For other related commands, see the section “Determining Dimensions and Locations” in the accompanying document `flowfram-code.pdf`.

4.3. Relative Locations

If you want a textual description to appear in the document of the relative location of one frame from another you can use:



```
\relativeframelocation{⟨type1⟩}{⟨ID1⟩}{⟨type2⟩}{⟨ID2⟩}
                                modifier: *
```

This produces a textual description of the relative location of the $\langle type1 \rangle$ frame identified by $\langle ID1 \rangle$ to the $\langle type2 \rangle$ frame identified by $\langle ID2 \rangle$ (the starred version references the frames by their IDL and the unstarred version references them by their IDN).



The relative locations are taken for the current page, regardless of whether either of the two frames are displayed on that page. If the current page is odd, then the frame settings for odd pages will be compared, otherwise the frame settings for even pages will be compared. However remember that the first paragraph of each page retains the settings in place at the start of the paragraph, so if the frames have different locations for odd and even pages, then `\relativeframelocation` may use the wrong page settings if it is used at the start of the page. You may prefer to use `\SaveRelativeFrameLocation` instead.

The text produced will be obtained with one of the following commands, which may be added to a language hook if required.



```
\FFaboveleft                                initial: above left
```

Text produced if the first frame is above left of the second frame.



```
\FFaboveright                                initial: above right
```

Text produced if the first frame is above right of the second frame.

`\FFabove`*initial:* above

Text produced if the first frame is above the second frame (but not to the right or left).

`\FFbelowleft`*initial:* below left

Text produced if the first frame is below left of the second frame.

`\FFbelowright`*initial:* below right

Text produced if the first frame is below right of the second frame.

`\FFbelow`*initial:* below

Text produced if the first frame is below the second frame (but not to the right or left).

`\FFleft`*initial:* on the left

Text produced if the first frame is to the left of the second frame (but not above or below).

`\FFright`*initial:* on the right

Text produced if the first frame is to the right of the second frame (but not above or below).

`\FFoverlap`*initial:* overlap

Text produced if both frames overlap.

Above

A frame is considered to be above another frame if the bottom edge of the first frame is higher than the top edge of the second frame.

Below

A frame is considered to be below another frame if the top edge of the first frame is lower than the bottom edge of the second frame.

Left

A frame is considered to be to the left of another frame if the right edge of the first frame is to the left of the left edge of the second frame.

Right

A frame is considered to be to the right of another frame if the left edge of the first frame is to the right of the right edge of the second frame.

There are some short cut commands for frames of the same type:

```
\reldynamicloc{⟨ID1⟩}{⟨ID2⟩}
```


*modifier: **

A shortcut for `\relativeframelocation` where both frame types are dynamic. The starred version references the dynamic frames by their IDL and the unstarred version references them by their IDN.

```
\relstaticloc{⟨ID1⟩}{⟨ID2⟩}
```

*modifier: **

A shortcut for `\relativeframelocation` where both frame types are static. The starred version references the static frames by their IDL and the unstarred version references them by their IDN.




```
\relflowloc{⟨ID1⟩}{⟨ID2⟩}
```

*modifier: **

A shortcut for `\relativeframelocation` where both frame types are flow. The starred version references the flow frames by their IDL and the unstarred version references them by their IDN.


These commands may be used in the optional argument of `\continueonframe` for frames that are on the same page. For example:



```
\begin{dynamiccontents}{1}
Some text in the first dynamic frame that goes on for
quite a bit longer than this example.
\continueonframe[continued \reldynamicloc{2}{1}]{2}
This text is in the second dynamic frame which is
somewhere on the same page.
\end{dynamiccontents}
```

Alternatively, they may be used in the default continued text, as in Example 3.

An alternative approach is to save the query in the aux file to ensure that the page counter is correct:




```
\SaveRelativeFrameLocation{⟨label⟩}{⟨type1⟩}{⟨ID1⟩}
{⟨type2⟩}{⟨ID2⟩}
```

*modifier: **

This saves the information and defers the calculation until the start of the next \LaTeX run. This means that the page number for the location in the document where `\SaveRelativeFrameLocation` was used will now be correct. The `⟨label⟩` argument is a label that may be used to reference the information and has the usual restrictions that apply to labels. The remaining arguments are as for `\relativeframelocation`.


On the next run, the information can be retrieved with:



```
\RefSavedRelativeLocation{<label>}
```


where *<label>* should match the label argument supplied to `\SaveRelativeFrameLocation`. This will produce the usual undefined reference double question mark ?? and a warning on the first run.

For example, this document defined a flow frame labelled `main` and a dynamic frame labelled `chaphead` which is used to display the chapter headings. The following code:




```
The dynamic frame is
\SaveRelativeFrameLocation*
{chapheadmain}% label
{dynamic}{chaphead}{flow}{main}% frames
\RefSavedRelativeLocation{chapheadmain}
of the flow frame.
```

produces:



The dynamic frame is on the left of the flow frame.

The result from the calculation is saved as one of the placeholder commands, `\FFabove` etc. You can test for any of these commands with:



```
\IfSavedRelativeLocationEq{<label>}{<cmd>}{<true>}{<false>}
```

This will expand to *<true>* if the given command matches or false if it doesn't match or if the label doesn't exist. In this case, no warning occurs for an undefined label. The second argument must be the actual placeholder command, not an expansion of it.

You will only be able to find out an exact match with `\IfSavedRelativeLocationEq`. For example, `\FFabove` will only match if the first frame is above the second frame but not to the right or to the left (that is, their horizontal positions overlap).

If you simply need to know more generally, you can use the following commands:

`\IfSavedRelativeLocationAbove{⟨label⟩}{⟨true⟩}{⟨false⟩}`

Expands to `⟨true⟩`, if the first frame is above the second frame without regard to their horizontal positions.

`\IfSavedRelativeLocationBelow{⟨label⟩}{⟨true⟩}{⟨false⟩}`

Expands to `⟨true⟩`, if the first frame is below the second frame without regard to their horizontal positions.

`\IfSavedRelativeLocationLeft{⟨label⟩}{⟨true⟩}{⟨false⟩}`

Expands to `⟨true⟩`, if the first frame is left of the second frame without regard to their vertical positions.

`\IfSavedRelativeLocationRight{⟨label⟩}{⟨true⟩}{⟨false⟩}`

Expands to `⟨true⟩`, if the first frame is right of the second frame without regard to their vertical positions.

For additional commands that determine the relative location of one frame from another, see the section “Determining the relative location of one frame from another” in the accompanying document `flowfram-code.pdf`.

The `flowfram` package has a number of commands which create frames in a predefined layout. These commands may only be used in the preamble. The distance between the flow frames created with these commands is given by the standard `\columnsep` length register.

`\adjustcolsep`

If you have more than two columns and you want space for any marginal notes (created with `\marginpar`) that may occur in the middle columns, you can use `\adjustcolsep` to automatically adjust the value of `\columnsep` to ensure that there's sufficient room. This is simply a shortcut that sets `\columnsep` to twice its existing value plus the value of `\marginparwidth`.

If you want to change the value of `\columnsep`, make sure you do it before using the column commands. Changing it afterwards will have no effect on any flow frames that have already been created.

5.1. Column Styles

The standard \LaTeX commands `\onecolumn` and `\twocolumn` are redefined to create one or two flow frames that fill the entire typeblock separated from each other (in the case of `\twocolumn`) by a gap of width `\columnsep`.

The final $\langle label \rangle$ optional argument the commands described below is retained for backward-compatibility. In early versions of `flowfram` that option occurred by chance rather than design as the some of the commands happened to end with `\newflow-frame` which picked up a following optional argument.

5. Predefined Layouts

5.1. Column Styles	111
5.2. Column Styles with an Additional Frame	115
5.3. Right to Left Columns	127
5.4. Backdrop Effects	128
5.4.1. Vertical stripe effects	129
5.4.2. Horizontal stripe effect	130
5.4.3. Background Frame	131
5.4.4. Vertical and Horizontal Rules . .	132

This chapter describes commands that create frames arranged in a predefined layout.

The syntax for these commands is slightly different:

```
\onecolumn [⟨page-list⟩] [⟨label⟩]
```

redefined by flowfram

Creates a flow frame that spans the typeblock with the given label and page list. If you want to specify a label, you will need to also supply the page list. The default is `all` for `⟨page-list⟩` and the frame's IDN for `⟨label⟩`.

```
\twocolumn [⟨page-list⟩] [⟨label⟩]
```

redefined by flowfram

Creates two flow frames that fit in the typeblock separated by the distance given by `\columnsep`. The first argument `⟨page-list⟩` is as for `\onecolumn`. The second argument may either be a single label, in which case it applies to the second column, or (v2.0+) two comma-separated labels where the first one should apply to the first flow frame and the second should apply to the second flow frame. For example:

```
\twocolumn[all][frame1, frame2]
```

The `RL` package option will define the columns starting from the right, so the right-hand column will be filled first. The default `LR` package option will define the columns starting from the left, so the left-hand column will be filled first. Likewise for all the other commands described in this section that create more than one flow frame.

The height of these flow frames may not be exactly as high as the typeblock, as their height is adjusted to make them an integer multiple of `\baselineskip`.

Example 4 shows a two-column document in draft mode where the flow frames were created with `\twocolumn`. Remember that the page geometry needs to be set first. The `lipsum` package is used to provide dummy text to pad out the document.

```
\documentclass[12pt]{article}
\usepackage[a4paper,margin=1in]{geometry}
\usepackage[draft]{flowfram}
\usepackage{lipsum}
\twocolumn% create two flow frames
\setflowframe{2}{border=plain}
% add border to second frame
\begin{document}
\lipsum[1-3]
\end{document}
```

Draft mode draws grey rectangles to show the location of the typeblock, frames and the margin area (where the text of `\marginpar` is placed). Note that the top border of both flow frames is slightly below the top border of the typeblock. This is due to the automatic vertical adjustment.


The plain border around the second flow frame is wider than the actual frame area. In this case, the `flowfram` package knows the appropriate offset for the plain border. Custom borders may require the use of the `offset` option. If you are creating the frames with `FlowframTk` then there's an area in which you can specify the inner padding between the border and the area for the text.

You can switch off the automatic height adjustment using the command:

```
\ffvadjustfalse
```

or switch it back on again with:

Example 4: Two Columns in Draft Mode



```
\ffvadjusttrue
```

You can test the current setting with the conditional:

```
\ifffvadjust <true>\else <false>\fi          initial: \iftrue
```

This setting applies to all the column commands described in this section.

```
\Ncolumn [ <page-list> ] { <n> } [ <label> ]
```

preamble only

Creates $\langle n \rangle$ column flow frames, each separated by a distance of `\columnsep`, adjusting their height according to the `\ifffvadjust` setting. This is similar to `\twocolumn` but the final optional argument is a single label for the last flow frame to be created.

```
\onecolumninarea [ <page-list> ] { <width> } { <height> } { <x> } { <y> }  
[ <label> ]
```

preamble only

This creates a single flow frame to fill the given area, adjusting its height according to the `\ifffvadjust` setting.

```
\twocolumninarea [ <page-list> ] { <width> } { <height> } { <x> } { <y> }  
[ <labels> ]
```

preamble only

Creates two column flow frames separated by a distance of `\columnsep` filling the area specified, adjusting their height according to the `\ifffvadjust` setting.

```
\Ncolumninarea[⟨page-list⟩]{⟨n⟩}{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}
[⟨labels⟩]
```



preamble only

This is a more general form of `\twocolumninarea` making $\langle n \rangle$ flow frames instead of two. The final optional argument is a single label for the last flow frame to be created.

5.2. Column Styles with an Additional Frame

As well as the column-style flow frames defined in §5.1, it is also possible to define $\langle n \rangle$ columns with an additional frame spanning either above or below them. There will be a vertical gap of approximately `\vcolumnsep` between the columns and the extra frame.

5

The height of the vertical gap may not be exactly `\vcolumnsep`, as the flow frames will be adjusted (if the default `\ffvadjusttrue` setting is in effect) so that their height is an integer multiple of `\baselineskip`, which may increase the gap.



In each of the following definitions, the argument $\langle page-list \rangle$ is the page list for which the frames are defined, $\langle n \rangle$ is the number of columns required, $\langle type \rangle$ is the type of frame to go above or below the columns (this may be one of: `flow`, `static` or `dynamic`). The area in which the new frames should fill is defined by $\langle width \rangle$, $\langle height \rangle$ (the width and height of the area) and $\langle x \rangle$, $\langle y \rangle$ (the position of the bottom left hand corner of the area relative to the bottom left hand corner of the typeblock.)

The height of the additional frame at the top or bottom of the columns is given by $\langle top-height \rangle$ and $\langle bottom-height \rangle$, respectively.



```
\onecolumntopinarea[⟨page-list⟩]{⟨type⟩}{⟨top-height⟩}{⟨width⟩}
{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

preamble only

Creates one flow frame with a $\langle type \rangle$ frame above it, filling the area specified. If the $\langle label \rangle$ option is supplied, it will be set as the label of the flow frame.



```
\twocolumntopinarea[⟨page-list⟩]{⟨type⟩}{⟨top-height⟩}{⟨width⟩}
{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

preamble only

Creates two column-style flow frames with a $\langle type \rangle$ frame above them, filling the area specified. If the $\langle label \rangle$ option is supplied, it will be set as the label of the last flow frame to be created.



```
\Ncolumntopinarea[⟨page-list⟩]{⟨type⟩}{⟨n⟩}{⟨top-height⟩}
{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

preamble only

Creates $\langle n \rangle$ column-style flow frames with a $\langle type \rangle$ frame above them, filling the area specified. If the $\langle label \rangle$ option is supplied, it will be set as the label of the last flow frame to be created.



```
\onecolumnbottominarea[⟨page-list⟩]{⟨type⟩}{⟨bottom-height⟩}
{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

preamble only

Creates one flow frame with a $\langle type \rangle$ frame underneath it, filling the area specified. If the $\langle label \rangle$ option is supplied, it will be set as the label of the flow frame.

```
\twocolumnbottominarea[⟨page-list⟩]{⟨type⟩}{⟨bottom-height⟩}
{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

preamble only

Creates two column-style flow frames with a $\langle type \rangle$ frame below them, filling the area specified. If the $\langle label \rangle$ option is supplied, it will be set as the label of the last flow frame to be created.

```
\Ncolumnbottominarea[⟨page-list⟩]{⟨type⟩}{⟨n⟩}{⟨top-height⟩}
{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

preamble only

Creates $\langle n \rangle$ column-style flow frames with a $\langle type \rangle$ frame below them, filling the area specified. If the $\langle label \rangle$ option is supplied, it will be set as the label of the last flow frame to be created.

The following commands are special cases of the above:

```
\onecolumnstopinarea[⟨page-list⟩]{⟨top-height⟩}{⟨width⟩}
{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\onecolumnstopinarea[⟨page-list⟩]{static}{⟨top-height⟩}
{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```



```
\onecolumnDtopinarea[⟨page-list⟩]{⟨top-height⟩}{⟨width⟩}
{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\onecolumnntopinarea[⟨page-list⟩]{dynamic}{⟨top-height⟩}
{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```



```
\onecolumnntop[⟨page-list⟩]{⟨type⟩}{⟨top-height⟩}[⟨label⟩]
```

preamble only

As `\onecolumnntopinarea` where the area is given by the typeblock.



```
\onecolumnStop[⟨page-list⟩]{⟨top-height⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\onecolumnntop[⟨page-list⟩]{static}{⟨top-height⟩}[⟨label⟩]
```



```
\onecolumnDtop[⟨page-list⟩]{⟨top-height⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\onecolumnstop [⟨page-list⟩] {dynamic} {⟨top-height⟩} [⟨label⟩]
```

```
\twocolumnstopinarea [⟨page-list⟩] {⟨top-height⟩} {⟨width⟩}
{⟨height⟩} {⟨x⟩} {⟨y⟩} [⟨label⟩]
```

preamble only

This is equivalent to:

```
\twocolumntopinarea [⟨page-list⟩] {static} {⟨top-height⟩}
{⟨width⟩} {⟨height⟩} {⟨x⟩} {⟨y⟩} [⟨label⟩]
```

```
\twocolumnDtopinarea [⟨page-list⟩] {⟨top-height⟩} {⟨width⟩}
{⟨height⟩} {⟨x⟩} {⟨y⟩} [⟨label⟩]
```

preamble only

This is equivalent to:

```
\twocolumntopinarea [⟨page-list⟩] {dynamic} {⟨top-height⟩}
{⟨width⟩} {⟨height⟩} {⟨x⟩} {⟨y⟩} [⟨label⟩]
```

```
\twocolumntop [⟨page-list⟩] {⟨type⟩} {⟨top-height⟩} [⟨label⟩]
```

preamble only

As `\twocolumntopinarea` where the area is the entire typeblock.

```
\twocolumnStop [⟨page-list⟩] {⟨top-height⟩} [⟨label⟩]
```

preamble only

This is equivalent to:

```
\twocolumntop [⟨page-list⟩] {static} {⟨top-height⟩} [⟨label⟩]
```

```
\twocolumnDtop [⟨page-list⟩] {⟨top-height⟩} [⟨label⟩]
```

preamble only

This is equivalent to:

```
\twocolumntop [⟨page-list⟩] {dynamic} {⟨top-height⟩} [⟨label⟩]
```

```
\NcolumnStopinarea [⟨page-list⟩] {⟨n⟩} {⟨top-height⟩} {⟨width⟩}
{⟨height⟩} {⟨x⟩} {⟨y⟩} [⟨label⟩]
```

preamble only

This is equivalent to:

```
\Ncolumntopinarea [⟨page-list⟩] {static} {⟨n⟩} {⟨top-height⟩}
{⟨width⟩} {⟨height⟩} {⟨x⟩} {⟨y⟩} [⟨label⟩]
```

```
\NcolumnDtopinarea[⟨page-list⟩]{⟨n⟩}{⟨top-height⟩}{⟨width⟩}
{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\NcolumnDtopinarea[⟨page-list⟩]{dynamic}{⟨n⟩}{⟨top-height⟩}
{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

```
\NcolumnDtop[⟨page-list⟩]{⟨type⟩}{⟨n⟩}{⟨top-height⟩}[⟨label⟩]
```

preamble only

As `\NcolumnDtopinarea` where the area is the entire typeblock.

```
\NcolumnDstop[⟨page-list⟩]{⟨n⟩}{⟨top-height⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\NcolumnDtop[⟨page-list⟩]{static}{⟨n⟩}{⟨top-height⟩}[⟨label⟩]
```

```
\NcolumnDtop[⟨page-list⟩]{⟨n⟩}{⟨top-height⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\Ncolumnstop[⟨page-list⟩]{dynamic}{⟨n⟩}{⟨top-height⟩}[⟨label⟩]
```

```
\onecolumnSbottominarea[⟨page-list⟩]{⟨bottom-height⟩}{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\onecolumnbottominarea[⟨page-list⟩]{static}{⟨bottom-height⟩}{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

```
\onecolumnDbottominarea[⟨page-list⟩]{⟨bottom-height⟩}{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\onecolumnbottominarea[⟨page-list⟩]{dynamic}{⟨bottom-height⟩}{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

```
\onecolumnbottom[⟨page-list⟩]{⟨type⟩}{⟨bottom-height⟩}[⟨label⟩]
```

preamble only

As `\onecolumnbottominarea` where the area is the entire typeblock.

```
\onecolumnSbottom[⟨page-list⟩]{⟨bottom-height⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\onecolumnbottom[⟨page-list⟩]{static}{⟨bottom-height⟩}[⟨label⟩]
```

```
\onecolumnDbottom[⟨page-list⟩]{⟨bottom-height⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\onecolumnbottom[⟨page-list⟩]{dynamic}{⟨bottom-height⟩}[⟨label⟩]
```

```
\twocolumnSbottominarea[⟨page-list⟩]{⟨bottom-height⟩}{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\twocolumnbottominarea[⟨page-list⟩]{static}{⟨bottom-height⟩}{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

```
\twocolumnDbottominarea[⟨page-list⟩]{⟨bottom-height⟩}{⟨width⟩}
{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\twocolumnbottominarea[⟨page-list⟩]{dynamic}{⟨bottom-
height⟩}{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

```
\twocolumnbottom[⟨page-list⟩]{⟨type⟩}{⟨bottom-height⟩}[⟨label⟩]
```

preamble only

As `\twocolumnbottominarea` where the area is the entire typeblock.

```
\twocolumnSbottom[⟨page-list⟩]{⟨bottom-height⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\twocolumnbottom[⟨page-list⟩]{static}{⟨bottom-height⟩}
[⟨label⟩]
```

```
\twocolumnDbottom[⟨page-list⟩]{⟨bottom-height⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\twocolumnbottom[⟨page-list⟩]{dynamic}{⟨bottom-height⟩}
[⟨label⟩]
```

```
\NcolumnSbottominarea[⟨page-list⟩]{⟨n⟩}{⟨bottom-height⟩}
{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\Ncolumnbottominarea[⟨page-list⟩]{static}{⟨n⟩}{⟨top-height⟩}
{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

```
\NcolumnDbottominarea[⟨page-list⟩]{⟨n⟩}{⟨bottom-height⟩}
{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\Ncolumnbottominarea[⟨page-list⟩]{dynamic}{⟨n⟩}{⟨top-
height⟩}{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

```
\Ncolumnbottom[⟨page-list⟩]{⟨type⟩}{⟨n⟩}{⟨top-height⟩}[⟨label⟩]
```

preamble only

As `\Ncolumnbottominarea` where the area is the entire typeblock.



```
\NcolumnSbottom[⟨page-list⟩]{⟨n⟩}{⟨top-height⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\Ncolumnbottom[⟨page-list⟩]{static}{⟨n⟩}{⟨top-height⟩}[⟨label⟩]
```



```
\NcolumnDbottom[⟨page-list⟩]{⟨n⟩}{⟨top-height⟩}[⟨label⟩]
```

preamble only

This is equivalent to:

```
\Ncolumnbottom[⟨page-list⟩]{dynamic}{⟨n⟩}{⟨top-height⟩}[⟨label⟩]
```

The top/bottom frame for each of the above commands is defined with:



```
\newframe[⟨page-list⟩]{⟨frame-type⟩}{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

*modifier: **
preamble only

This is essentially the same as:

```
\new⟨frame-type⟩frame[⟨page-list⟩]{⟨width⟩}{⟨height⟩}{⟨x⟩}{⟨y⟩}[⟨label⟩]
```

5.3. Right to Left Columns

The default behaviour for the column style commands defined in §§5.1 & 5.2 above is to create the flow frames from left to right. However if you are typesetting from right to left, you will probably prefer to define the flow frames in the reverse order. This can be done via the package option `RL`. Alternatively you can use the command:

```
\lefttorightcolumnsfalse
```

before using commands such as `\twocolumn` or `\Ncolumn`. To switch back to left-to-right columns use the `LR` option or:

```
\lefttorightcolumnstrue
```

You can test the current setting with the conditional:

```
\iflefttorightcolumns <true>\else <false>\fi  
initial: \iftrue
```

Changing the setting only affects new flow frames created with subsequent column commands and does not affect any flow frames that have already been created or any flow frames created explicitly with `\newflowframe`.

Remember that it's the order of definition that determines the next flow frame to be selected by the output routine (that's valid for the current page). This setting simply switches round the order of definition in the column-style shortcut commands.

5.4. Backdrop Effects

Static frames can be used to produce a backdrop, and there are a number of commands that define static frames and automatically set the `backcolor` attribute to create a rectangular patch of colour.

In the following definitions, $\langle page-list \rangle$ is the page list for which those static frames are defined (`all` is the default). The arguments $\langle L1 \rangle, \dots, \langle Ln \rangle$ are the labels to assign to the 1st, ..., $\langle n \rangle$ th new frame that will be created by the applicable command.

The arguments $\langle C1 \rangle, \dots, \langle Cn \rangle$ are the colour specifications for the $\langle L1 \rangle, \dots, \langle Ln \rangle$ frame. The colour specification must be completely enclosed in the $\langle C1 \rangle$ etc argument braces. For example `{ [rgb] { 1, 0, 1 } }` (one argument) not `[rgb] { 1, 0, 1 }` (optional argument followed by mandatory argument).

For the horizontal stripes: $\langle x-offset \rangle$ is the amount by which the frames should be shifted horizontally (0pt by default), $\langle W1 \rangle$ is the width of frame $\langle L1 \rangle$, and so on up to $\langle Wn \rangle$, the width of frame $\langle Ln \rangle$.

For the vertical stripes: $\langle y-offset \rangle$ is the amount by which the frames should be shifted vertically (0pt by default), $\langle H1 \rangle$ is the height of frame $\langle L1 \rangle$, and so on up to $\langle Hn \rangle$, the height of frame $\langle Ln \rangle$.



Unlike the earlier commands, these commands are all relative to the actual page, not the typeblock. So an $\langle x-offset \rangle$ of 0pt indicates the first vertical frame is flush with the left hand edge of the page, and a $\langle y-offset \rangle$ of 0pt indicates the first horizontal frame is flush with the bottom edge of the page. This is because backdrops tend to span the entire page, not just the typeblock.

5.4.1. Vertical stripe effects

```
\vtwotone [⟨page-list⟩] [⟨x-offset⟩] {⟨W1⟩} {⟨C1⟩} {⟨L1⟩} {⟨W2⟩} {⟨C2⟩}
{⟨L2⟩}
```

Defines two static frames to create a two-tone vertical stripe effect. (This command was used to create the coloured background on the title page of this document.)

```
\vNtone [⟨page-list⟩] [⟨x-offset⟩] {⟨n⟩} {⟨W1⟩} {⟨C1⟩} {⟨L1⟩} ... {⟨Wn⟩}
{⟨Cn⟩} {⟨Ln⟩}
```


This is similar to `\vtwotone` but with `⟨n⟩` static frames instead of two.

```
\vtwotonebottom [⟨page-list⟩] [⟨x-offset⟩] {⟨H⟩} {⟨W1⟩} {⟨C1⟩}
{⟨L1⟩} {⟨W2⟩} {⟨C2⟩} {⟨L2⟩}
```

This is similar to `\vtwotone` but the static frames are only `⟨H⟩` high, instead of the entire height of the page. The frames are aligned along the bottom edge of the page.


```
\vtwotonetop [⟨page-list⟩] [⟨x-offset⟩] {⟨H⟩} {⟨W1⟩} {⟨C1⟩} {⟨L1⟩}
{⟨W2⟩} {⟨C2⟩} {⟨L2⟩}
```

This is similar to `\vtwotone` but the static frames are only `⟨H⟩` high, instead of the entire height of the page. The frames are aligned along the top edge of the page. (This command was used to create the border effect along the top of every page in this document. Two `\vtwotonetop` commands were used, one for the even pages, and the other for the odd pages.)



```
\vNtonebottom[⟨page-list⟩][⟨x-offset⟩]{⟨n⟩}{⟨H⟩}{⟨W1⟩}{⟨C1⟩}{⟨L1⟩}...{⟨Wn⟩}{⟨Cn⟩}{⟨Ln⟩}
```


This is a general version of `\vtwotonebottom` for $\langle n \rangle$ frames instead of two.



```
\vNtonetop[⟨page-list⟩][⟨x-offset⟩]{⟨n⟩}{⟨H⟩}{⟨W1⟩}{⟨C1⟩}{⟨L1⟩}...{⟨Wn⟩}{⟨Cn⟩}{⟨Ln⟩}
```


This is a general version of `\vtwotonetop` for $\langle n \rangle$ frames instead of two.

5.4.2. Horizontal stripe effect




```
\htwotone[⟨page-list⟩][⟨y-offset⟩]{⟨H1⟩}{⟨C1⟩}{⟨L1⟩}{⟨H2⟩}{⟨C2⟩}{⟨L2⟩}
```

This defines two static frames to create a two-tone horizontal stripe effect.



```
\hNtone[⟨page-list⟩][⟨y-offset⟩]{⟨n⟩}{⟨H1⟩}{⟨C1⟩}{⟨L1⟩}...{⟨Hn⟩}{⟨Cn⟩}{⟨Ln⟩}
```

This is similar to `\htwotone` but with $\langle n \rangle$ static frames instead of two.



```
\htwotoneleft[⟨page-list⟩][⟨y-offset⟩]{⟨W⟩}{⟨H1⟩}{⟨C1⟩}{⟨L1⟩}{⟨H2⟩}{⟨C2⟩}{⟨L2⟩}
```

This is similar to `\htwotone` but the statics are only $\langle W \rangle$ wide, instead of the entire width of the page. The frames are aligned along the left edge of the page.

```
\htwotoneright [⟨page-list⟩] [⟨y-offset⟩] {⟨W⟩} {⟨H1⟩} {⟨C1⟩} {⟨L1⟩}
{⟨H2⟩} {⟨C2⟩} {⟨L2⟩}
```

This is similar to `\htwotone` but the statics are only $\langle W \rangle$ wide, instead of the entire width of the page. The frames are aligned along the right edge of the page.

```
\hNtoneleft [⟨page-list⟩] [⟨y-offset⟩] {⟨n⟩} {⟨W⟩} {⟨H1⟩} {⟨C1⟩}
{⟨L1⟩} ... {⟨Hn⟩} {⟨Cn⟩} {⟨Ln⟩}
```

This is a general version of `\htwotoneleft` for $\langle n \rangle$ frames instead of two.

```
\hNtoneright [⟨page-list⟩] [⟨y-offset⟩] {⟨n⟩} {⟨W⟩} {⟨H1⟩} {⟨C1⟩}
{⟨L1⟩} ... {⟨Hn⟩} {⟨Cn⟩} {⟨Ln⟩}
```

This is a general version of `\htwotoneright` for $\langle n \rangle$ frames instead of two.

5.4.3. Background Frame

```
\makebackgroundframe [⟨page-list⟩] [⟨label⟩]
```

Creates a single static frame covering the entire page. The new frame will be given the IDL $\langle label \rangle$, if provided.

If this frame is given a background colour, it should be created before any other static frames otherwise it will obscure all other static frames created before it.

5.4.4. Vertical and Horizontal Rules

You can create vertical or horizontal rules between two frames using the commands described below. The arguments $\langle type-1 \rangle$ and $\langle type-2 \rangle$ identify the frame type (`static`, `flow` or `dynamic`). For the unstarred version, the frames should be identified by their IDN and for the starred version they should be identified by their IDL.

`\insertvrule[$\langle y-top \rangle$][$\langle y-bottom \rangle$]{ $\langle type-1 \rangle$ }{ $\langle ID1 \rangle$ }{ $\langle type-2 \rangle$ }{ $\langle ID2 \rangle$ }` *modifier: **

Creates a new static frame which fits between $\langle type-1 \rangle$ frame identified by $\langle ID1 \rangle$ and $\langle type-2 \rangle$ frame identified by $\langle ID2 \rangle$.

The new frame's y position and height are calculated from the lowest point of the lowest frame (of $\langle ID1 \rangle$ and $\langle ID2 \rangle$) to the highest point of the highest of the reference frames. The first optional argument $\langle y-top \rangle$ (default 0pt) extends the height of the new frame by that much above the highest point.

The second optional argument $\langle y-bottom \rangle$ (default 0pt) increases the height of the new frame by that much but also lowers the y position by that amount. If either of the optional arguments are negative, the frame will be shortened instead of extended.

The contents of this new frame are set to a vertical rule that extends the full height of the frame. The width of the rule is given by:

`\ffcolumnseprule` *initial: 2pt*

This has changed as from version 1.09: versions prior to 1.09 used `\columnseprule` (provided by the L^AT_EX kernel).

The vertical rule drawn by `\insertvrule` is created using the command:

```
\ffvrule{⟨offset⟩}{⟨width⟩}{⟨height⟩}
```

This can be redefined if a more ornate rule is required (see Example 5).

The command:

```
\ffruleddeclarations
```

initial: empty

can be redefined to set declarations that affect how the rule is drawn. The most likely use of this command is to set the rule colour. Any redefinition of `\ffruleddeclarations` must come before the static frame is created. (Remember that the contents of a static frame are set in a box so the declaration is used at that point.)

```
\inserthrule[⟨x-left⟩][⟨x-right⟩]{⟨type-1⟩}{⟨ID1⟩}{⟨type-2⟩}{⟨ID2⟩}
```

*modifier: **


This creates a new static frame which fits between `⟨type-1⟩` frame identified by `⟨ID1⟩` and `⟨type-2⟩` frame identified by `⟨ID2⟩`.

The new frame's `x` position and width are calculated from the leftmost point of the furthest left frame (of `⟨ID1⟩` and `⟨ID2⟩`) to the rightmost point of the furthest right of the reference frames. The first optional argument `⟨x-top⟩` (default 0pt) extends the width of the new frame by that much above the rightmost point.

The second optional argument `⟨x-bottom⟩` (default 0pt) increases the width of the new frame by that much but also lowers the `x` position by that amount. If either of the optional arguments are negative, the frame will be shortened instead of extended.

The contents of this new frame are set to a horizontal rule that extends the full width of the frame. The height of the rule is given by `\ffcolumseprule`.



The horizontal rule drawn by `\inserthrule` is created using the command:



```
\ffhrule{<offset>}{<width>}{<height>}
```

This can be redefined if a more ornate rule is required (see Example 5). The horizontal rule is also governed by `\ffruledeclarations`. As with `\insertvrule`, any redefinition of these commands must be made before `\inserthrul` to have an effect.

Example 5 creates two flow frames with a static frame above (with `\twocolumnStop`) and the creates a vertical rule between the two flow frames and a horizontal rule between the top static frame and the two flow frames, but first the rules are redefined to use a zigzag pattern (achieved with the `tikz` package).

```
\usepackage{flowfram}
\usepackage{tikz}
\usetikzlibrary{decorations.pathmorphing}
\twocolumnStop{1in}
\renewcommand{\ffvrule}[3]{%
  \hfill \tikz{%
    \draw[decorate,decoration=zigzag,
      line width=#2,yshift=-#1]
      (0,0) -- (0pt,#3); }%
  \hfill \mbox{}}
\insertvrule{flow}{1}{flow}{2}

\renewcommand{\ffhrule}[3]{%
  \tikz{%
    \draw[decorate,decoration=zigzag,
      line width=#3,xshift=-#1] (0,0) -- (#2,0pt);
  }}
\inserthrul{static}{1}{flow}{1}
```

The lipsum package is used for filler text. The document body sets the content for the first static frame (the top one):

```
\setstaticcontents{1}{Top Frame}\lipsum[1-5]
```

Remember that because the static frame contents are set in a box, any change to `\ffvrule` or `\ffhrule` must occur before the corresponding `\insertvrule` or `\inserthrule` for the change to have an effect.

Example 5: Rules



Top Frame

~~~~~  
Lorem ipsum dolor sit amet, consectetur enim. Praesent euismod nunc eu purus. Do-  
adipiscing elit. Ut purus elit, vestibulum ut, nec bibendum quam in tellus. Nullam cursus  
placrat ac, adipiscing vitae, felis. Curabitur pulvinar lectus. Donec et mi. Nam vulputate  
dictum gravida mauris. Nam arcu libero, no- metus eu enim. Vestibulum pellentesque felis  
nummy eget, consectetur id, vulputate a, ma- eu massa.  
gna. Donec vehicula augue eu neque. Pellen- Quisque ullamcorper placerat ipsum. Cras  
tesque habitant morbi tristique senectus et ne- nibh. Morbi vel justo vitae lacus tincidunt ul-  
tus et malesuada fames ac turpis egestas. Mau- trices. Lorem ipsum dolor sit amet, consec-  
ris ut leo. Cras viverra metus rhoncus sem- tetuer adipiscing elit. In hac habitasse pla-  
ces. Phasellus eu tellus sit amet tortor gra- tea dictumst. Integer tempus convallis augue.  
vida placerat. Integer sapien est, iaculis in. Etiam facilisis. Nunc elementum fermentum  
pretium quis, viverra ac, nunc. Praesent eget wisi. Aenean placerat. Ut imperdiet, enim sed  
sem vel leo ultrices bibendum. Aenean fauci- ac pulvinar elit purus eget enim. Nunc vitae  
bus. Morbi dolor nulla, malesuada eu, pulvinar tortor. Proin tempus nibh sit amet nisl. Viva-  
at, mollis ac, nulla. Curabitur auctor semper mus quis tortor vitae risus porta vehicula.  
nulla. Donec varius orci eget risus. Duis nibh Fusce mauris. Vestibulum luctus nibh at  
mi, congue eu, accumsan eleifend, sagittis quis, lectus. Sed bibendum, nulla a faucibus semper,  
diam. Duis eget orci sit amet orci dignissim ru- leo velit ultricies tellus, ac venenatis arcu wisi  
trum. vel nisl. Vestibulum diam. Aliquam pellentes-  
que, augue quis sagittis posuere, turpis lacus  
Nam dui ligula, fringilla a, euismod soda- que, congue quam, in hendrerit risus eros eget felis.  
les, sollicitudin vel, wisi. Morbi auctor lorem Maecenas eget erat in sapien mattis porttitor.  
non justo. Nam lacus libero, pretium at, lo- Vestibulum porttitor. Nulla facilisi. Sed a tur-  
bortis vitae, ultricies et, tellus. Donec aliquet, pis eu lacus commodo facilisis. Morbi fringilla,  
tortor sed accumsan bibendum, erat ligula ali- wisi in dignissim interdum, justo lectus sagittis  
quet magna, vitae ornare odio metus a mi. dui, et vehicula libero dui cursus dui. Mauris  
Morbi ac orci et nisl hendrerit mollis. Suspen- tempor ligula sed lacus. Duis cursus enim ut  
disse ut massa. Cras nec ante. Pellentesque augue. Cras ac magna. Cras nulla. Nulla ege-  
a nulla. Cum sociis natoque penatibus et ma- stas. Curabitur a leo. Quisque egestas wisi  
gnis dis parturient montes, nascetur ridiculus eget nunc. Nam feugiat lacus vel est. Curabi-  
mus. Aliquam tincidunt urna. Nulla ullam- tur consectetur.  
corper vestibulum turpis. Pellentesque cursus  
luctus mauris.  
~~~~~  
Nulla malesuada porttitor diam. Donec fe-
lis erat, congue non, volutpat at, tincidunt tri-
stique, libero. Vivamus viverra fermentum fe-
lis. Donec nonummy pellentesque ante. Pha-
sellus adipiscing semper elit. Proin fermentum
massa ac quam. Sed diam turpis, molestie vi-
tae, placerat a, molestie nec, leo. Maecenas
lacinia. Nam ipsum ligula, eleifend at, accu-
msan nec, suscipit a, ipsum. Morbi blandit
ligula feugiat magna. Nunc eleifend consequat
lorem. Sed lacinia nulla vitae enim. Pellen-
tesque tincidunt purus vel magna. Integer non

6.1. Thumbtabs

On the right hand side of the odd pages and on the left hand side of even pages in this document, there is a blue rectangle with the chapter number in it. This is a thumbtab, and it gives you a rough idea whereabouts in the document you are when you quickly flick through the pages (of a hard copy). Each thumbtab is in fact a dynamic frame.

There are two dynamic frames per thumbtab: the thumbtab index shown in the table of contents and the main thumbtab shown in the applicable part of the document. These frames are given special labels: `thumbtabindex⟨n⟩` for the $\langle n \rangle$ th thumbtab index and `thumbtab⟨n⟩` for the $\langle n \rangle$ th thumbtab.

With FlowframTk you can also define separate thumbtabs for even pages in two-sided documents. These have special labels `eventhumbtabindex⟨n⟩` for the $\langle n \rangle$ thumbtab index frame shown on even pages and `eventhumbtab⟨n⟩` for the $\langle n \rangle$ thumbtab frame shown on even pages.

Options that govern the thumbtab settings are listed in §1.2.1.

```
\makethumbtabs [⟨y-offset⟩] {⟨height⟩} [⟨section-type⟩]
```

preamble only

If you want thumbtabs in your document, you need to add `\makethumbtabs` in the preamble. This reads information in from the `ttb` file created during the previous \LaTeX run. As with the table of contents, you need a rerun to ensure that the thumbtab information is correct.

Each dynamic frame corresponding to a thumbtab and thumbtab index is then defined by `\makethumbtabs` with the contents set according to the information read from the `ttb` file. If a dynamic frame with the corresponding special label has already been defined, that will be used instead of defining a new frame. (This will be the case with any package

6. Thumbtabs and Minitocs

6.1. Thumbtabs	137
6.2. Minitocs	144

This chapter describes how to create thumbtabs and minitocs, such as those used in this document.

or class files that have been exported from FlowframTk where thumbtab frames have been setup.)



If you have used FlowframTk and you haven't defined enough thumbtab frames, `\makethumbtabs` will fall back on the default thumbtab frame style for the missing frames.

When `\makethumbtabs` creates a dynamic frame, the $\langle height \rangle$ argument is the height of each thumbtab frame. The default y position puts the first thumbtab level with the top of the typeblock and each following thumbtab is shifted below the last by $\langle height \rangle$. The first optional argument $\langle y-offset \rangle$ (a dimension) will shift all the thumbtabs vertically by $\langle y-offset \rangle$. The width of each thumbtab is given by:



`\thumbtabwidth`

initial: 1cm

This value may be changed with `\setlength` but only changes that are made before `\makethumbtabs` will have any effect. The `evenx` position will automatically be calculated. If the frame was already defined, no change will be made to its attributes.



The dimension settings will be ignored if the thumbtab frames have already been defined.

The final optional argument $\langle section-type \rangle$ indicates what section unit should be used for the thumbtabs. If omitted, $\langle section-type \rangle$ obtained by expanding:



`\defaultthumbtabtype`

initial: varies

This command should expand to the control sequence name (no backslash) of the applicable section type. The default definition is `chapter` if `\chapter` is defined, otherwise it's `section`.

Make sure that you have set all your preferred thumbtab settings before using `\make-thumbtabs`. For example:

```
\flowframsetup{
  thumbtabs=number,
  thumbtab-text=normal
}
\makethumbtabs{0.75in}
```

Once the thumbtab dynamic frames have been defined and setup, the thumbtab indexing must be enabled.

```
\enablethumbtabs
```

This should be placed at the point where you want the thumbtab indexing to start.

There will be no thumbtabs if you don't have *both* `\makethumbtabs` and `\enablethumbtabs` in your document.

You may put `\enablethumbtabs` in the preamble (after `\makethumbtabs`) in which case any front matter sectional units may have associated thumbtabs, depending on the `matter-thumbtabs` option. Alternatively, place `\enablethumbtabs` just before the first sectional unit that should appear as a thumbtab. For example:

```
\tableofcontents
\mainmatter
\enablethumbtabs
\chapter{Introduction}
```

You can stop indexing thumbtabs with:

```
\disablethumbtabs
```

This should be placed before the sectional unit that shouldn't have a thumbtab. For example:

```
End of last chapter.
\appendix
\disablethumbtabs
\chapter{Supplementary Material}
```

The thumbtab index frames will automatically be shown in the table of contents unless you have used `adjust-toc=off`, which prevents `flowfram` from redefining `\tableofcontents`. If you have done this and want the thumbtab indexes to appear elsewhere, you can switch them on with:

```
\thumbtabindex[<page-list>]
```

The optional argument *<page-list>* indicates which pages the thumbtab frames should be shown on.

There are commands available to customized the format of the thumbtab content.

```
\thumbtabhyperlinkformat{<anchor>}{<text>}{<height>}
```

This command is used when the content should have a hyperlink to the start of the associated sectional unit. The `hyperref` package needs to be loaded to support this. If `hyperref` is loaded after `flowfram`, `\thumbtabhyperlinkformat` will automatically be redefined to use `\hyperlink`.

Regardless of whether or not `hyperref` has been loaded, `\thumbtabhyperlinkformat` will format the text with:

```
\thumbtabformat{<text>}{<height>}
```

The behaviour of this command varies according to the `thumbtab-text` option. You can redefine `\thumbtabformat` if you prefer, but the `thumbtab-text` options will no longer have an effect after that.

```
\thumbtabindexformat{<anchor>}{<text>}{<height>}
```

This command is used to format the content of the thumbtab index frames. The default definition just uses `\thumbtabhyperlinkformat`. The `\thumbtabindexformat` command will be redefined by the `thumbtab-links` option.


```
\thumbtabregularformat{<anchor>}{<text>}{<height>}
```

This command is used to format the content of the thumbtab (non-index) frames. The default definition just uses `\thumbtabformat`. The `\thumbtabregularformat` command will be redefined by the `thumbtab-links` option.

Since thumbtab frames are just dynamic frames, it is possible to change their attributes with `\setdynamicframe`. However, the dynamic frames won't be defined until

`\makethumbtabs` finds the relevant information in the `ttb` file. This means that you will get an error on the first run when the frames are not defined.

Instead, the thumbtab frame attributes can be changed with:



```
\setthumbtab{⟨index⟩|all}{⟨key=value list⟩}
```

This sets the attributes `⟨key=value list⟩` for the dynamic frames associated with the thumbtab with the given `⟨index⟩` (starting from 1 for the first thumbtab). Only a warning occurs if the dynamic frames haven't been defined.

For example:




```
\setthumbtab{1}{bgcolor=[rgb]{0.15,0.15,1}}
```

This is essentially equivalent to:

```
\setdynamicframe*
{thumbtabindex1,thumbtab1}
{bgcolor=[rgb]{0.15,0.15,1}}
```

Note that `⟨index⟩` isn't the same as the frame's IDN. The first argument may be the keyword `all`, which indicates all thumbtabs frames.

To just change the settings for the thumbtab index, use:



```
\setthumbtabindex{⟨index⟩|all}{⟨key=value list⟩}
```

This is like `\setthumbtab` but only changes the thumbtab index frames. For example:

```
\setthumbtabindex{1}{backcolor=[rgb]{0.15,0.15,1}}
}
```

This is essentially equivalent to:

```
\setdynamicframe*
{thumbtabindex1}
{backcolor=[rgb]{0.15,0.15,1}}
```

By default, the thumbtabs have a grey background (unless you have created them with FlowframTk). In this document, I set the background colours with:

```
\setthumbtab{1}{backcolor=[rgb]{0.15,0.15,1}}
\setthumbtab{2}{backcolor=[rgb]{0.2,0.2,1}}
\setthumbtab{3}{backcolor=[rgb]{0.25,0.25,1}}
\setthumbtab{4}{backcolor=[rgb]{0.3,0.3,1}}
\setthumbtab{5}{backcolor=[rgb]{0.35,0.35,1}}
\setthumbtab{6}{backcolor=[rgb]{0.4,0.4,1}}
\setthumbtab{7}{backcolor=[rgb]{0.45,0.45,1}}
\setthumbtab{8}{backcolor=[rgb]{0.5,0.5,1}}
\setthumbtab{9}{backcolor=[rgb]{0.55,0.55,1}}
```

I then defined my own custom command for the frame style:

```
\newcommand{\thumbtabstyle}{%
\centering\bfseries\large\sffamily
}
```

```
\setthumbtab{all}{valign=c,style=
thumbtabstyle,textcolor=white}
```

6.2. Minitocs

In this document, after each chapter heading, there is a mini table of contents (mini-toc) for that chapter. To enable mini-tocs, use the command:

```
\enableminitoc[⟨section-type⟩]
```

preamble only

This enables a mini-toc at the start of the given sectional unit. If present, the optional argument *⟨section-type⟩* should be the control sequence name (no backslash) of the section command. If omitted, the default is to use the same as that used by thumbtabs.

The mini-toc will normally appear immediately after the corresponding section heading. If you prefer the mini-toc to appear in a dynamic frame, you can use:

```
\appenddfminitoc{⟨ID⟩}
```

*modifier: **
preamble only

This appends the mini-toc to the dynamic frame identified by *⟨ID⟩* (the IDN for the unstarred version or the IDL for the starred version). The mini-toc support needs to be enabled first with `\enableminitoc`.

For example, in this document, I have:

```
\appenddfminitoc*{chaphead}
```

Recall from §2.4.1 that `\ChapterInDynamic` causes the corresponding sectioning command to reset the contents of the identified dynamic frame. The `\appenddfminitoc` command will cause the corresponding sectioning command to append to the contents of the associated dynamic frame.

This means that if you have something like:

```
\ChapterInDynamic*{<label>}
\enableminitoc
\appenddfminitoc*{<label>}
```

for the same dynamic frame `<label>`, then `\chapter` will first set the contents with the section heading and will then append the mini-toc. If `\ChapterInDynamic` isn't used or has a different frame, then the behaviour of `\appenddfminitoc` will depend on whether or not the `clear` attribute has been set on the mini-toc frame. If the `clear` attribute is not set then the mini-toc code will only be appended once. (Otherwise the frame would end up accumulating all the mini-tocs.)

The style of the mini-toc text is governed by:

```
\minitocstyle{<content>}
```

The default behaviour is to simply reset the font and text colour to normal. The argument is the mini-toc content. Note that this style isn't applied to the dynamic frame's `style` as the reason for appending the mini-toc content is because there may be other content in the frame, such as the chapter heading. The `\minitocstyle` command is placed inside a group so any declarations will be scoped.

The mini-toc has vertical spacing before and after it.

```
\beforeminitocskip initial: 0pt
```

The gap before the mini-toc.

`\afterminitocskip`

initial: `\baselineskip`



The gap after the mini-toc. These are both lengths and can be changed with `\setlength`.

7.1. Macros

The following macros can be changed using `\renewcommand`:

```
\setffdraftcolor
```

Sets the colour of the bounding boxes when displayed in draft mode (see §1.4). The default definition is:

```
\color[gray]{0.8}
```

For example, if you want a darker grey, do:

```
\renewcommand{\setffdraftcolor}{\color[gray]{0.3}}
}
```

```
\setffdrafttypeblockcolor
```

Sets the colour of the typeblock outline when displayed in draft mode. The default definition is:

```
\color[gray]{0.9}
```

```
\fflabelfont
```

7. Global Settings

7.1. Macros	147
7.2. Lengths	148
7.3. Counters	149

This section describes style macros, lengths and counters used by the `flowfram` package.

Sets the font for the annotation labels shown in draft mode. The default definition is:

```
\small\sffamily
```

7.2. Lengths

The following are lengths, which can be changed using `\setlength`:

```
\fflabelsep
```

initial: 1pt

The distance from the right hand side of the bounding box at which to place the annotation.

```
\flowframesep
```

The gap between the text of the frame and its border, for the standard border types. This is initialised to `\fboxsep` when `flowframe` loads. It won't be automatically updated if `\fboxsep` is later changed.

```
\flowframerule
```

The width of the frame's border, if using a border given by a frame making command that uses `\fboxsep` to set its border width (for example, `\fbox`).

```
\sdfparindent
```

initial: 0pt

The default paragraph indentation within static or dynamic frames. This may be overridden for individual frames with the `parindent` attribute.

`\vcolumnsep`*initial:* `\columnsep`

The approximate vertical distance between the top frame and the column frames when using `\Ncolumnstop` etc. (The height of the flow frame may be adjusted if the `ffadjust` setting is on.) This length should be changed before the frames are defined for the change to have effect.

`\columnsep`

The `\columnsep` length is provided by the \LaTeX kernel and is used in \LaTeX 's normal two-column mode. With `flowfram` it's used for the horizontal distance between the column frames that are created with commands such as `\Ncolumn`. This length should be changed before the frames are defined for the change to have effect.

7.3. Counters

The following are counters that can be accessed via `\value{<counter-name>}` or `\the-
<counter-name>`.

The values of these counters may be referenced but should not be modified. They are automatically incremented by the commands.

**`maxstatic`**

No

The total number of static frames that have been defined so far. You can use this value to reference the most recently defined static frame.

No

maxflow

The total number of flow frames that have been defined so far. You can use this value to reference the most recently defined flow frame.

No

maxdynamic

The total number of dynamic frames that have been defined so far. You can use this value to reference the most recently defined dynamic frame.

No

maxthumbtabs

The total number of thumbtabs.

No

absolutepage

The absolute page number.

No

thisframe

Stores the IDN of the current flow frame. You can label and reference the IDN using:


`\labelflowidn{<label>}`

This is analogous to the standard `\label` command, but will always refer to the IDN of the current flow frame. It can then be referenced using `\ref`.

Avoid using `\labelflowidn` or `thisframe` in the contents of a static or dynamic frame.

displayedframe

This counter is reset at the start of each page and is incremented each time a flow frame is selected by the output routine. If all flow frames are displayed on the current page then this will have the same value as `thisframe`. However, if some flow frames are invalid for the current page, the values of `displayedframe` and `thisframe` may be different. You can label the `displayedframe` counter using:

```
\labelflow{<label>}
```

The label may then be referenced with `\ref`. For example, if your document has a column layout:

```
This text is about hippos\labelflow{hippos}.
...
% Somewhere else in the document:
See column~\ref{hippos} on page~\pageref{hippos}
for information on hippos.
```

Avoid using `\labelflow` or `displayedframe` in the contents of a static or dynamic frame.

FlowframTk is a Java graphical application that may be used to create images from shapes that are defined by control points (vector graphics). Bitmaps and text can also be added. The latest stable version can be found on CTAN¹ but experimental releases are also available on GitHub.² The application can be invoked from the command line with:

```
flowframtk
```

Depending on how it has been installed, you may also be able to start it from your operating system's application menu or from a desktop shortcut.

8.1. Export to Image

An image created in FlowframTk can be exported as a \LaTeX (`\tex`) file that contains a `pgfpicture` environment (provided by the `pgf` package) with the basic layer commands that replicate (as near as possible) the image created in FlowframTk. By way of example, figure 1.1 was created using FlowframTk (with the isometric grid).

Any document that inputs one of these exported files will need to include the `pgf` package, but the exported file may also contain some bespoke commands needed to emulate certain effects, such as outlined text. These are provided by the `flowframtkutils` package (see §8.4) which automatically loads `pgf`.

If all you want is to include the exported image in your document, then you don't need to load the `flowfram` package in your document (but you will need to ensure that `flowfram` is installed in order to load the supplementary `flowframtkutils` package, if required). The `flowfram` package is too fragile and has the potential to conflict with too many other classes or packages to load it unnecessarily.

¹ctan.org/pkg/flowframtk

²<https://github.com/nlct/flowframtk/releases>

8. FlowframTk

8.1. Export to Image	153
8.2. Compute Parameters for <code>\parshape</code> or <code>\shapepar</code>	154
8.3. Export to Document Class or Package .	154
8.4. The <code>flowframtkutils</code> Package	155
8.4.1. Options	156
8.4.2. Provided Commands	157

8.2. Compute Parameters for `\parshape` or `\shapepar`

The `shape` attribute is only available for static or dynamic frames. It can be set automatically if you want to use FlowframTk's export to document class or package function (§8.3) but if you want a shaped paragraph in a flow frame or if you don't need to use the `flowfram` package but would like a shaped paragraph in an ordinary document, then you can create the desired shape in FlowframTk and use the “Parshape” or “Shapepar” function (be sure to set the normal font size first in FlowframTk's \TeX configuration settings). This will calculate the parameters for the applicable command and create a file that contains the command and arguments needed to shape a paragraph.

Simply `\input` the file (that was created by FlowframTk's Parshape or Shapepar function) at the start of the paragraph that should be shaped. Take care not to insert a paragraph break between inputting the file and the start of the text. See the FlowframTk user manual for further details.



Since `\parindent` is a \TeX primitive and `shapepar` provides generic code, this function may be used with other \TeX formats, such as plain \TeX .

8.3. Export to Document Class or Package

Whilst creating images is something that can also be done by other vector graphics applications (some of which may create more readable `tikz` code), FlowframTk can also create a \LaTeX package (`sty`) or class file (`cls`) that uses the `flowfram` package. In this case, instead of reproducing the image, the shapes may be used to identify flow frames, static frames or dynamic frames. The definitions (`\newflowframe`, `\newstaticframe` and `\newdynamicframe`) will be written to the exported `sty` or `cls` file. You may find that using this graphical interface is an easier approach to defining frames than trying to

calculate the locations and dimensions using \LaTeX commands. When you use FlowframTk's export function to create a document class or package, the created file will contain the code to automatically load both flowfram and flowframtkutils (but make sure that you have at least version 0.8.8 of FlowframTk).

When using FlowframTk to construct flowfram data, you need to first establish the typeblock and then identify the shapes that should represent frames. Any shapes that aren't identified as such won't be exported. (This is useful if, for example, you have shapes that provide guides for the positioning of other shapes.) You can choose whether the shape itself should be used as a border (or background, if it's filled) for the corresponding frame or whether to simply use the shape's bounding box as the location and size of the frame.



When using the FlowframTk export function, don't set the `backcolor` or `bordercolor` attributes. Instead, use the line paint and fill paint settings in FlowframTk.

You may also define dynamic frames with special labels but make sure you have an up-to-date version of both flowfram and FlowframTk to ensure they are properly implemented. With at least FlowframTk version 0.8.8, you can use the Flow Frame Wizard to ensure that the correct labels are used.

8.4. The flowframtkutils Package



```
\usepackage[<options>]{flowframtkutils}
```

The flowframtkutils package is provided with flowfram v2.0+ to assist with files that have been exported from FlowframTk. It provides the bespoke commands that may be written to those files. Ensure that you have at least version 0.8.8 of FlowframTk to support newer commands.



The flowframkutils package doesn't load the flowfram package as it may be simply required when an image is exported as pgf code. However, flowframkutils does automatically load the pgf package as it's likely to be needed in either the image export or the class/package export.

8.4.1. Options

All options that can be passed to flowfram can also be passed to a package (`sty`) or class (`cls`) created by FlowframTk. However, flowframkutils itself only has the following options, which can only be set when the package is loaded:



textpath= \langle boolean \rangle

default: **true**; initial: **false**

If true, when flowframkutils is loaded, it will automatically load the decorations.text PGF library after loading the pgf package. Note that this library doesn't support all of FlowframTk's text-path settings. See the FlowframTk documentation for further details.



outline= \langle boolean \rangle

default: **true**; initial: **false**

If true, when flowframkutils is loaded, it will try to provide the appropriate support for outline text and will redefine `\jdroutline` as appropriate.

If pdf \LaTeX or Lua \LaTeX is used, this option will input the `pdf-trans.tex` file, which contains generic pdf \TeX code to render text as an outline. This code includes pdf \TeX primitives, so if Lua \LaTeX is used, the `luatex85` package will automatically be loaded with this option to ensure they are defined.


If a different engine is used, this option will load the `pst-char` package instead, which will use PSTricks to render the outline.

8.4.2. Provided Commands

Many of the flowfram-related commands provided by the flowframtkutils package aren't intended for general use, as they are provided to simplify the code written by FlowframTk to ensure that the bespoke files are correctly integrated with the flowfram package with the class/package export function.

Most of the user-level commands described here are those used when exporting an image to a file containing the pgfpicture environment. (The “jdr” prefix is a throwback to FlowframTk's original name, JpgfDraw.)

If you export to a complete document, FlowframTk version 0.8.8 and above will search for the flowframtkutils package using `kpsewhich`. If it's found, FlowframTk will assume it's available for use. If not, or if an older version of FlowframTk is used, it will provide the definition of the “jdr” commands if they are required.

`\includeteximage[⟨key=value list⟩]{⟨filename⟩}`


The `\includeteximage` command is provided with `\ProvideDocumentCommand` rather than defined as a new command, as it may be defined in a similar manner by other packages. This command isn't written to any exported file by FlowframTk but is provided by flowframtkutils to include an exported image (tex) file in a document. You can simply input the file with commands like `\input`, but `\includeteximage` provides some extra features.

The filename identified by `⟨filename⟩` is input but the command first locally sets the input search path to match the graphics search path used by `\includegraphics`. This means that you can save your exported image tex file to the same location as your other image files.

If the optional argument is present, a transformation can be applied to the image. For example, if it turns out to be too large for the page, you could go back to FlowframTk and shrink it or you can use the scaling options in `\includeteximage`. The recognised keys are just a subset of those recognised by `graphicx`: `scale`, `angle`, `width`,

height and alt. Bear in mind that scaling the image will also scale any text within the image.

```
\jdroutline{<pdf-trans code>}{<pst-char code>}{<text>}
```

If enabled by the `outline` option, `\jdroutline` will attempt to render `<text>` as an outline using `<pdf-trans code>` (if `pdf-trans.tex` was loaded) or `<pst-char code>` (if `pst-char` was loaded). If not enabled, this command will generate a warning and just do `<text>`.


For example, large bold “ABC” rendered with a green outline that’s filled with red:

```
\jdroutline
{2 Tr 0 1 0 rg 1 0 0 RG}
{fillstyle=solid,linecolor=green,fillcolor=red}
{\bfseries\Huge ABC}
```

```
\jdrimagebox{<image>}
```


Used for encapsulated images, `\jdrimagebox` is designed to prevent problems if numerical rounding errors cause the image to be larger than the available area. It’s used when FlowframTk exports to a complete document that encapsulates the image. (Rather than exporting to a `tex` file that can be input from an existing document.)

The following commands are only written to exported files by FlowframTk v0.8.8+ if it’s detected that `flowframtkutils` is available.



```
\flowframtkimageinfo{⟨key=value list⟩}
```

If FlowframTk was instructed to include the title and creation date, this command will be written to the exported (tex) document file. This is only applicable when the export to a complete document is used, rather than export to a file just containing the image code. Available options:




```
title={⟨text⟩}
```

Set the title with `\flowframtkSetTitle{⟨text⟩}`. (The title is the image's description.)




```
creationdate={⟨PDF date⟩}
```

Set the creation date with `\flowframtkSetCreationDate{⟨PDF date⟩}`.



```
\flowframtkSetCreationDate{⟨PDF date⟩}
```

If `hyperref` has been loaded, this will use `\hypersetup` to set the PDF creation date, otherwise if `\pdfinfo` has been defined that will be used instead.



```
\flowframtkSetTitle{⟨title⟩}
```

If `hyperref` has been loaded, this will use `\hypersetup` to set the document title meta data, otherwise if `\pdfinfo` has been defined that will be used instead. Awkward

characters within the title will be marked up with:

```
\flowframtkimgtitlechar{<char>}{<PDF replacement>}
```

This normally just expands to `<char>` but if `\pdfinfo` is required, then this will expand to the detokenized `<PDF replacement>`. For example, if the image's description was set to “A House (with a pond)” in FlowframTk, and the image is exported as a complete document with meta data, then the document preamble would contain (for the given timestamp):

```
\flowframtkimageinfo{
  title={A House \flowframtkimgtitlechar{({}{\ (}
with a pond\flowframtkimgtitlechar{)}{){\ )}},
  creationdate={D:20250815192214+01'00' }
}
```

If you import from a format that can change paragraph justification, the import function will use the kernel commands `\raggedleft`, `\raggedright` and `\centering`. However, there is no equivalent kernel command to reset the paragraph justification, so when full justification is specified, the import function will use:

```
\flowframtkNoRagged
```

This command is defined to restore the paragraph justification back to the way it was when `flowframtkutils` was loaded, which should typically be full justification. This may not be appropriate if the settings were changed after `flowframtkutils` was loaded.

In general, in this type of situation, the code obtained from the import function is likely to need some tidying up. In which case, you may prefer to remove this command and ensure that any justification declarations are scoped.

If you provide a description for an object, it will be included as a comment. This can help to identify the relevant parts of the code but you may prefer to have hooks to allow you to

add content from the document (rather than editing the exported image file). For example, to add tagging for accessibility or to uncover elements of the image in beamer. With FlowframTk v0.8.8+, you can specify what type of hook you want: paired, encapsulated or no hook.

```
\flowframtkstartobject{⟨n⟩}{⟨Java class
name⟩}{⟨description⟩}{⟨tag⟩}{⟨pgf point⟩}{⟨width⟩}{⟨height⟩}
```

If this hook is added to the image, it will always be paired with a matching closing hook:

```
\flowframtkendobject{⟨n⟩}{⟨Java class
name⟩}{⟨description⟩}{⟨tag⟩}{⟨pgf point⟩}{⟨width⟩}{⟨height⟩}
```

By default, the above pair do nothing.

Alternatively, you can choose to encapsulate each object, which will instead use the following hook:

```
\flowframtkencapobject{⟨n⟩}{⟨Java class
name⟩}{⟨description⟩}{⟨tag⟩}{⟨pgf point⟩}{⟨width⟩}{⟨height⟩}{⟨object⟩}
```

By default, this simply does the final argument *⟨object⟩*, which is the code to draw the object.

The common arguments in these hooks are:

⟨n⟩

A number that's unique for each object in a given image. This argument in `\flowframtkendobject` must always be the same as its matching `\flowframtkstartobject`. The numbering starts at 0 for the entire image and then increments for each object within the image, descending down groups.

⟨Java class name⟩

The Java class name of the object. For example, `JDRPath` for a path (which may consist of lines, curves and moves), `JDRText` for text or `JDRBitmap` for bitmaps.

This is the class responsible for writing the PGF code to render (as closely as possible) the object. That is, the final argument for `\flowframtkencapobject` or the content between `\flowframtkstartobject` and `\flowframtkendobject`. This is true, even if the object needs to be temporarily converted for the export. For example, a text area with gradient paint may be converted to a filled path if the “To Path” export setting has been applied. The PGF code will then be path construction code not `\pgftext`, but the class name will still be `JDRText`.

⟨description⟩

The description assigned to the object or empty if no description was set.

⟨tag⟩

The tag or space-separated tag list assigned to the object or empty if no tag was set.

⟨pgf point⟩

The lower left point of the object’s bounding box, in the form `\pgfpoint{⟨x⟩}{⟨y⟩}`.

⟨width⟩

The width of the object’s bounding box.

⟨height⟩

The height of the object’s bounding box.

A simplistic way of adding overlays would be to export using the paired commands and `add \pause`:

```
\renewcommand{\flowframtkendobject}[7]{\pause}
```

The *flowframtkutils* package provides functions that may be used in the definition of the markup pairs `\flowframtkstartobject` and `\flowframtkendobject`. First make sure that you export to an image with the “Paired” setting on. Then anywhere before the image is included in the document these command may be redefined.

```
\FlowframTkBeginScopeIfGroup{<class name>}
```

Designed for use in the definition of `\flowframtkstartobject`, this command will insert `\begin{pgfscope}` if `<class name>` is `JDRGroup`, otherwise it will do nothing.

```
\FlowframTkEndScopeIfGroup{<class name>}
```

Designed for use in the definition of `\flowframtkendobject`, this command will insert `\end{pgfscope}` if `<class name>` is `JDRGroup`, otherwise it will do nothing.

These two commands will need to be used in pairs to ensure that the `pgfscope` environment is correctly started and ended. For example:

```
\renewcommand\flowframtkstartobject[7]{%
  \FlowframTkBeginScopeIfGroup{#2}%
}%
\renewcommand\flowframtkendobject[7]{%
  \FlowframTkEndScopeIfGroup{#2}%
}
```

The `flowframtkutils` package provides functions that may be used in the definition of `\flowframtkencapobject`. First make sure that you export to an image with the “Encapsulated” setting on. Then anywhere before the image is included in the document this command may be redefined.

```
\FlowframTkScopeIfGroup{<class name>}{<object>}
```

Designed for use in the definition of `\flowframtkencapobject`, this command will encapsulate `<object>` within the `pgfscope` environment if `<class name>` is `JDRGroup`, otherwise it will just do `<object>`. You may find this useful if you have set one or more clipping paths and you want to limit the scope. In this case, you just need to redefine `\flowframtkencapobject`:

```
\renewcommand\flowframtkencapobject[8]{%
  \FlowframTkScopeIfGroup{#2}{#8}%
}
```

There is a more complicated low-level function for use with beamer. Rather than explicitly redefining `\flowframtkencapobject` (which would require switching on $\text{\LaTeX}3$ syntax) you can simply use:

```
\FlowFramTkUtilsSetOverlayEncap[<key=value list>]
```

This redefines `\flowframtkencapobject` to use the low-level function:

```
\flowframtkutils_uncover_encap:nnnnnnnn {<n>}
{<Java class name>} {<description>} {<tag>} {<pgf point>} {<width>}
{<height>} {<object>}
```

(There shouldn't be any need to use this function directly.)

This recognises the settings that may be set in the optional argument of `\FlowFramTkUtilsSetOverlayEncap` to govern the way that objects are uncovered.

The default is to use beamer's `\uncover` command but two helper functions are used (which both required \LaTeX 3 syntax to be enabled if you need to redefine them).

```
\flowframtkutils_uncover:nn {<number>} {<content>}
```

Uncovers for a single slide. The default definition is:

```
\uncover<number>>{<content>}
```

```
\flowframtkutils_uncover_from:nn {<number>} {<content>}
```

Uncovers from a slide. The default definition is:

```
\uncover<number>->{<content>}
```

If you later want to change the settings you can use:

```
\FlowFramTkUtilsOverlayEncapSetup{<key=value list>}
```

This should be placed before the image is input into the document but bear in mind that the settings are local and there may be interference if they are changed within the same frame that has the overlays.

The `\flowframtkutils_uncover_encap:nnnnnnnn` function is still a little experimental, but it basically works as follows:

- When $\langle n \rangle$ is 0 (that is, the entire image), the bounding box is saved and some other initialisation is performed.

- When $\langle n \rangle$ is greater than 0, the overlay setting is searched for:
 - With the `auto-overlay=true` option, an integer variable is incremented for all object types except groups. This value is used as the overlay. Each object will be uncovered according to the order in which it was written to the exported file.
 - With the `auto-overlay=false` option, the `tag-overlay` setting is checked. If that has an overlay identified for the object's tag then that will be used. If not, the `object-overlay` setting is checked. If that has an overlay identified for the object's type then that will be used. If not, the `fallback-overlay` setting is checked. If that has been set then that will be used. If not, the current object will be visible with no overlay specification.
- When $\langle n \rangle$ is greater than 0 and the `annotate` setting is not `false`, then after the object has been draw according to the above overlay settings an annotation will be added if applicable. The annotation consists of text with optionally a line from the object's bounding box to the text, which is offset according to the `dx` and `dy` settings. By default the line has an arrow head at the start. This may be changed with the `annotate-arrow` setting. Whether or not the object has an annotation is determined by `annotate-text`. The annotation overlay is determined by the `annotate` setting.

For example, assuming that the file `image.tex` was created by FlowframTk with the “Object Markup” option set to “Encapsulated”:

```
\documentclass{beamer}
\usepackage{flowframtkutils}
\FlowFramTkUtilsSetOverlayEncap
[
  object-overlay={path = 1, text = 2},
  annotate,
```

```

    \annotate-text=description-or-tag
  ]
\begin{document}
\begin{frame}
\frametitle{An Image}
\centering
\input{image}
\end{frame}
\end{document}

```

There are two ways of adding annotations. You can either add the text and, if applicable, a line with an arrow head to the image in FlowframTk and tag them. Then you can use the `tag-overlay` option to uncover them. Alternatively, you can use the `annotate` option to automatically add annotations based on each object's tag or description. This second method is less precise as the annotation is placed relative to the object's bounding box, which may be at a distance from a non-rectangular shape, but may be sufficient for simple images.

Available options are listed below.

uncover=*<value>*

initial: **from**

Determines whether or not overlays should be used for image objects and, if so, should the object just be shown on a single overlay or from a certain number.

uncover=**single**

Uncover for a single slide.

uncover=from

Uncover from a slide.

uncover=false

Don't have overlays for image objects (but annotations may still be overlaid).

annotate=<value>

default: true; initial: false

Determines whether or not annotations should be added and, if so, what overlays should be used for annotations. If this setting is on but not annotation text is available for a given object then the annotation will be skipped. The annotation text, if available, is offset from the object's bounding box. Optionally a line may be drawn from the bounding box to the text. The "annotation" refers to the text and, if present, the line.

annotate=single

Uncover annotation, if applicable, for a single slide. That is, use `\uncover<num>>{<annotation>}`.

annotate=from

Uncover annotation, if applicable, from a slide. That is, use `\uncover<num>->{<annotation>}`.

annotate=match

Match the `uncover` setting.

annotate=true

Enable annotations without changing the overlay setting.

annotate=false

Don't show annotations.

annotate-position=*<value>*

initial: auto

If annotations should be added, this setting indicates in which direction the annotation should be.

annotate-position=auto

Automatically determine the direction based on the object's relative position within the image.

annotate-position=north


Place the annotation above the object.

annotate-position=northeast

Place the annotation above right of the object.


annotate-position=east

Place the annotation right of the object.



```
annotate-position=southeast
```

Place the annotation below right of the object.



```
annotate-position=south
```

Place the annotation below the object.



```
annotate-position=southwest
```

Place the annotation below left of the object.




```
annotate-position=west
```

Place the annotation left of the object.



```
annotate-position=northwest
```

Place the annotation above left of the object.



```
annotate-arrow= { <key=value list> }
```

default: **show**

If annotations should be added, this setting governs the annotation arrow. Available settings are described in §8.4.2.2.



```
annotate-text= { <value> }
```

default: **description**

The text used for the annotation. If the text is empty or no mapping has been provided then

there won't be an annotation for the object.

`annotate-text=hide`

No annotation text (which means no arrow either, regardless of the `annotate-arrow` setting).

`annotate-text=description`

If the object has a description, use that as the annotation text.

`annotate-text=tag`

If the object has a tag, use that as the annotation text.

`annotate-text=description-or-tag`

If the object has a description, use that as the annotation text, otherwise if the object has a tag use that.

`annotate-text=tag-map`

If the object has a tag and a mapping has been set with `tag-text`, use the mapping as the annotation text.

`tag-text={ ⟨key=value list⟩ }`

Sets up the mappings for use with `annotate-text=tag-map`, where the key in `⟨key=value list⟩` is the tag and the value is the text to use for that tag. For example, if the image has some objects that have the tag “window” and some have the tag “door”:

```
tag-text={
  window = {A Window},
  door = {A Door}
}
```

auto-overlay={ *<boolean>* } *default: true; initial: false*

If true, auto-increment the overlay for each object that's not a group. (Groups are excluded as their content is nested.)

tag-overlay={ *<key=value list>* }

If `auto-overlay=false`, set up the tag overlays, where the key in *<key=value list>* is the tag and the value is the overlay number. For example, if the image has some objects that have the tag “building”, some have the tag “window” and some have the tag “door”:

```
tag-overlay={
  building = 1,
  window = 2,
  door = 3
}
```


Within *<key=value list>*, the value part should be a number but may also be empty (the equal sign is still needed). This means that there shouldn't be an overlay for an object with that tag. This is different from omitting the tag from the list as it prevents the `object-overlay` and `fallback-overlay` checks.

If the *<key=value list>* is not empty, this option automatically sets `auto-overlay=false`.




object-overlay = { *<key=value list>* }

If `auto-overlay=false`, set up the object overlays, where the key in *<key=value list>* identifies the object and the value is the overlay number.



If you set an overlay for groups but objects within the group also have an overlay, this will cause nested `\uncover`.


The key may be any of: `group`, `path`, `text`, `text-path`, `symmetric-path`, `scaled-pattern`, `spiral-pattern`, `rotational-pattern` or `bitmap`. For example:



```
object-overlay={
  bitmap = 1,
  path = 2,
  text = 3
}
```

Within *<key=value list>*, the value part should be a number but may also be empty (the equal sign is still needed). This means that there shouldn't be an overlay for an object of that type. This is different from omitting the object type from the list as it prevents the `fallback-overlay` check.

If the *<key=value list>* is not empty, this option automatically sets `auto-overlay=false`.



fallback-overlay = { *<key=value list>* }

If `auto-overlay=false`, and if an object doesn't have an overlay identified by

either `tag-overlay` or `object-overlay`, then use this fallback. Available keys for `<key=value list>` are listed in §8.4.2.1.

8.4.2.1. Fallback Overlay Options

These are available settings for use in the `fallback-overlay` option value. They can also be set with `\keys_set:nn` where the module is `flowframtkutils / overlay / fallback`.

enable=`<boolean>`

default: **true**; initial: **false**

If true, enables fallback overlay setting. This means that if an overlay is identified by either `tag-overlay` or `object-overlay` then the overlay will be set to the default value (for non-group objects).

fixed=`{ <number> }`

If fallback overlay setting enabled, set the default overlay to `<number>`.

increment

If fallback overlay setting enabled, set the default overlay to a number that's incremented for each use of the fallback.

8.4.2.2. Annotation Arrow Options

These are available settings for use in the `annotate-arrow` option value. They can also be set with `\keys_set:nn` where the module is `flowframtkutils / overlay / arrow`.

show= $\langle\text{boolean}\rangle$ *default: true; initial: true*

If annotations should be added, show an arrow in addition to the text. For example:

`annotate-arrow={show=true}`

If this is the only `annotate-arrow` setting, then it can be written more compactly:

`annotate-arrow=show`**hide**= $\langle\text{boolean}\rangle$ *default: true; initial: false*

The inverse of `show`. If annotations should be added, don't show an arrow (only show the text).

dx= $\{ \langle\text{dim}\rangle \}$ *default: 1cm*

If annotations should be added, the horizontal displacement from the start of the arrow. This is also the horizontal displacement for the annotation text, regardless of whether or not the arrow is shown.

dy= $\{ \langle\text{dim}\rangle \}$ *default: 1cm*

If annotations should be added, the vertical displacement from the start of the arrow. This is also the vertical displacement for the annotation text, regardless of whether or not the arrow is shown.

color= { \langle colour-name \rangle }

initial: **black**

The colour to use for the annotation arrow, if shown. The value may be empty to indicate the current stroke colour should be used, otherwise it should be a colour name suitable for use in `\pgfsetstrokecolor`.

start= { \langle arrow-name \rangle }

initial: **<**

The start arrow marker to use for the annotation arrow, if shown. The value may be empty to indicate there should be no start arrow, otherwise it should be suitable for use in `\pgfsetarrowsstart`. The line starts at the object's bounding box so that's where the start arrow will be placed. A non-rectangular shape may be some distance away from this point.

Remember to include the `arrows.meta` PGF library if you want to use any of the meta arrows. For example with:

```


 $\$ 


```

the preamble requires:

```


\usepgflibrary{arrows.meta}


```


end= { \langle arrow-name \rangle }

initial: **empty**

The end arrow marker to use for the annotation arrow, if shown. The value may be

empty to indicate there should be no end arrow, otherwise it should be suitable for use in `\pgfsetarrowsend`. The line ends on the annotation text's boundary, the location determined according to the `\pgftext` anchor.

For example:



```
annotate-arrow={  
  show,  
  dx=2cm,  
  dy=1cm,  
  start={},  
  end={>}  
}
```


For an up-to-date list of frequently asked questions, see the `flowfram` FAQ.¹

9.1. General Queries

1. If all my flow frames are only defined on, say, pages 1–10, what happens if I then add some extra text so that the document exceeds 10 pages?

The output routine will create a new flow frame the size of the typeblock and use that.

2. Can I use the formatted page number in page lists?

No.

3. Why not?

When the output routine finishes with one flow frame it looks for the next flow frame defined on that page. If there are none left, it then searches through the page list of all the defined flow frames to see if the next page lies in that range. If there are none defined on that page, it ships out that page, and tries the next page. This gives rise to two problems:

- a) `LaTeX` is not clairvoyant. If it is currently on page 14, and on the next page the page numbering changes to A, it has no way of knowing this until it has reached that point, which it hasn't yet. So it is looking for a flow frame defined on page 15, not on page A.
- b) How does `LaTeX` tell if page C lies between pages A and D? It would require an algorithm that can convert from a formatted number back to an integer. Given that there are many different ways of formatting the value of a counter (besides the standard Roman and alphabetical formats) it would be impossible to write an algorithm to do this for some arbitrary format.

¹dickimaw-books.com/faq.php?category=flowfram

9. Troubleshooting

9.1. General Queries	179
9.2. Unexpected Output	182
9.3. Error Messages	184

This chapter should be consulted if you experience any problems using the `flowfram` package.

4. Can I have an arbitrarily shaped frame?

You can assign certain irregular shapes to static or dynamic frames, using the `shape` key (see §3.2). Note that the bounding box will still appear as a rectangle with the dimensions of the given frame which may not correspond to the assigned shape. This function is not available for flow frames.

5. Why has the text from my flow frame appeared in a static or dynamic frame?

Assuming you haven't inadvertently set that text as the contents of the static or dynamic frame, the frames are most likely overlapping (see §1.1). In an attempt to clarify what's going on, suppose you have defined a static frame, a dynamic frame and two flow frames. The following is an approximate analogy (not strictly accurate as \TeX may make several attempts to fill in the flow frames due to penalties etc):

\TeX has a sheet of paper on the table, and has pencilled in a rectangle denoting the typeblock. The paper is put to one side for now. \TeX also has four rectangular sheets of transparent paper. The first (which I shall call sheet 1) represents the static frame, the next two (which I shall call sheets 2 and 3) represent the flow frames, and the last one (which I shall call sheet 4) represents the dynamic frame.

\TeX starts work on filling sheet 2 with the document text. Once it has put as much text on that sheet as it considers possible (according to its views on aesthetics), it puts sheet 2 into the "in tray", and then continues on sheet 3. While it's filling in sheets 2 and 3, if it encounters a command or environment that tells it what to put in the static frame, it fills in sheet 1 and then puts sheet 1 into the "in tray" and resumes where it left off on sheet 2 or 3. Similarly, if it encounters a command that tells it what to put in the dynamic frame, it stops what it's doing, fills in sheet 4, then puts sheet 4 into the "in tray", and resumes where it left off.

Only when it has finished sheet 3 (the last flow frame defined on that page), will it gather together all the transparent sheets, and fix them onto the page starting with sheet 1 through to sheet 4, measuring the bottom left hand corner of each transparent sheet relative to the bottom left hand corner of the typeblock. \TeX will then put that page aside, and start work on the next page. If two or more of the transparent sheets

overlap, you will see through the top one into the one below (unless of course the top one has been painted over, either by setting a background colour, or by adding an image that has a non-transparent background).

Note that it's also possible that the overlap is caused by an overfull hbox that's causing the text to poke out the side of the flow frame into a neighbouring frame. Check the log file for warnings or use the `draft` option to the document class which will place a filled rectangle on the end of overfull lines.

6. Why do I get lots of overfull hbox messages?

Probably because you have narrow frames. It's better to use ragged right formatting when the frames are narrow.

7. Why do I keep getting multiply-defined warnings?

Probably because you have used `\label` in a static or dynamic frame that is displayed on more than one page. Try using the `clear` key to ensure that the frame is always cleared at the end of each page.

8. What happens if I use a command or environment that switches to two-column mode (e.g. `theindex`)?

The behaviour depends on the `column-changes` setting (see §1.2.3).

9. How do I change the vertical alignment of material inside a static or dynamic frame?

Use the `valign` attribute.

10. How do I compute the distance from the edge of the page instead of the typeblock?

See §4.1.

11. Is there a GUI I can use to make it easier to create the frames?

Yes, `FlowframTk` (see §7.3).

9.2. Unexpected Output

1. The lines of text at the beginning of my flow frames are the wrong width.

This is a problem that will occur if you have flow frames with different widths, as the change in `\hsize` does not come into effect until a paragraph break. So if you have a paragraph that spans two flow frames, the end of the paragraph at the beginning of the second flow frame will retain the width it had at the start of the paragraph at the bottom of the previous flow frame. You can fix the problem by inserting `\framebreak` at the point where the frame break occurs (see §2.1.1).

2. My frames shift to the right when I add a border.

This may occur if you use a border that is not recognised by the `flowfram` package. You will need to set the offset using the `offset` key (see §2.4.4).

3. I have a vertical white strip along the right hand side of every page.

This can happen if you have, say, an A4 document, and `ghostscript` has letter as the default paper size. You can change the default paper size by editing the file `gs_init.ps`. Change:

```
% Optionally choose a default paper size other than U.S. letter.
% (a4)
```

to:

```
% Optionally choose a default paper size other than U.S. letter.
(a4)
```

4. I don't have any output.

All your flow frames are empty. `TeX` doesn't put the frames onto the page until it has finished putting text into the flow frames. So if there is no text to go in the flow frames it won't output the page. If you only want the static or dynamic frames filled

in, and nothing outside of them, just do `\mbox{}\clearpage`. This will put an invisible something with zero area into your flow frame, but it's enough to convince T_EX that the document contains some text.

5. The last page hasn't appeared.

See the previous answer.

6. There is no paragraph indentation inside my static or dynamic frames.

The paragraph indentation in static or dynamic frames is governed by the length `\sdfparindent` which is set to 0pt by default. To make the indentation the same as that used by flow frames place the following in the preamble:

```
\setlength{\sdfparindent}{\parindent}
```

Alternatively, you can use the `parindent` attribute if different indentation is required for different frames.

7. My section numbering is in the wrong order.

Remember that the contents of the dynamic frames are not set until the page is shipped out, and the contents will be set in the order of IDN, so if you have any sectioning commands occurring within dynamic frames, they may not be set in the same order as they are in your input file.

8. The contents of my static or dynamic frame have shifted to the left when I used `\parshape`.

This will happen if your `\parshape` specification exceeds the line width. For example:



```
\parshape=1 0.4\linewidth 0.7\linewidth
```

This specifies a line with overall length 1.1\linewidth which is too long.

9.3. Error Messages

1. Illegal unit of measure (pt inserted)

All lengths must have units. Remember to include the units when defining new frames. The following frame options require lengths: `width`, `height`, `x`, `y`, `oddx`, `oddy`, `evenx`, `eveny`, `parindent` and `offset` (although `offset` can also have the value `compute`).

2. Missing number, treated as zero

L^AT_EX is expecting a number. There are a number of possible causes:

- a) You have used an IDL instead of an IDN. If you want to refer to a frame by its label, you need to remember to use the starred versions of the `\set-
<type>frame` commands, or when setting the contents of static or dynamic frames.
- b) When specifying page lists, you have mixed keywords with page ranges. For example: `1, even` is invalid.

3. Flow frame IDL '*label*' already defined

All IDLs within each frame type must be unique. There are similar error messages for duplicate IDLs for static frames and dynamic frames.

4. Can't find flow frame id

You have specified a non-existent flow frame IDL. There are similar error messages for static frames and dynamic frames. Check to make sure you have spelt the label correctly, and check you are using the correct frame type command. (For

example, if a static frame has the IDL “mylabel”, and you attempt to do `\set-flowframe*{mylabel}{\langle options \rangle}`, then you will get this error, because “mylabel” refers to a static frames not a flow frame.)

5. Key 'clear' is boolean

The `clear` key can only have the values `true` or `false`.

6. Key 'clear' not available

The `clear` key is only available for static or dynamic frames.

7. Key 'style' not available

The `style` key is only available for dynamic frames.

8. Key 'margin' not available

The `margin` key is only available for flow frames.

9. Key 'shape' not available

The `shape` key is only available for static or dynamic frames.

10. Dynamic frame style '`\langle style \rangle`' not defined

The specified style `\langle style \rangle` must be the name of a command without the preceding backslash. It is possible that you have mis-spelt the name, or you have forgotten to define the command.

11. Argument of `\fbbox` has an extra }

This error will occur if you do, say, `border=\fbbox` instead of `border=fbbox`. Remember not to include the initial backslash.

12. Not in outer par mode

You can not have floats (such as figures, tables or marginal notes) in static or dynamic frames. If you want a figure or table within a static or dynamic frame use `staticfigure` or `statictable`.

13. Something's wrong—maybe missing `\item`

Assuming that all your list type of environments start with `\item`, this may be caused by something going wrong with the `toc` (table of contents), `ttb` (thumbtab) or `aux` (auxiliary) files in the previous run. Try deleting them, and try again.

14. `\verb` illegal in command argument

As a general rule, you can't use verbatim in a command argument. This rule applies to all the commands defined by the `flowfram` package. See also below.

15. I get “`\verb` illegal in command argument” when using a command inside the `dynamiccontents` environment.

You can not use commands or environments inside either the `dynamiccontents` or `dynamiccontents*` environment.

A.1. Terms

Bounding box

The bounding box of a frame is the area allocated for the contents of that frame. However the text may not completely fill that area, and it is possible that the text may overflow that area.

Dynamic frame

Frames in which text is fixed in place, but the contents are re-typeset each time the frame is displayed.

Flow frame

The frames in a document such that the contents of the document environment flow from one frame to the next in the order that they were defined. There must be at least one flow frame on every page.

FlowframTk

A Java application with a graphical user interface which can be used to construct frames for use with the flowfram package. It can also be used to create vector graphics images which can be exported as `tex` files containing a `pgfpicture` environment (defined by the `pgf` package). The supplementary package `flowframtkutils` provided with flowfram will need to be loaded by any document that inputs these files. The `flowframtkutils` package will also be automatically added to any `cls` or `sty` files created by `flowframtk` (version 0.8.8 onwards). The latest stable release is available on CTAN¹ or experimental releases can be found on GitHub.² FlowFramTk was originally called JpgfDraw (a Java `pgf`-code generating drawing application). Ensure you have at least version 0.8.8 to use the features mentioned in this manual.

¹ctan.org/pkg/flowframtk

²<https://github.com/nlct/flowframtk/releases>

A. Glossary

A.1. Terms	187
A.2. Symbols	190

Footer frame

A special dynamic frame with the label `footer` created either with `\makedfheaderfooter` or via `FlowframTk`'s export function, or the special dynamic frame with the label `evenfooter` that may be created with `FlowframTk`. If `evenfooter` doesn't exist, the `footer` frame will be used for the page footer on both odd and even pages. If `evenfooter` does exist, it will be used as the page footer for even pages if the document two-sided setting is on. This special behaviour must be enabled either with `\makedfheaderfooter` or via `FlowframTk`.

Frame

A rectangular area of the page in which text can be placed (not to be confused with a frame making command). There are three types: flow, static and dynamic.

Frame making command

A \LaTeX command which places some kind of border around its argument. For example: `\fbox`.

Header frame

A special dynamic frame with the label `header` created either with `\makedfheaderfooter` or via `FlowframTk`'s export function, or the special dynamic frame with the label `evenheader` that may be created with `FlowframTk`. If `evenheader` doesn't exist, the `header` frame will be used for the page header on both odd and even pages. If `evenheader` does exist, it will be used as the page header for even pages if the document two-sided setting is on. This special behaviour must be enabled either with `\makedfheaderfooter` or via `FlowframTk`.

Identification label (IDL)

A unique label which can be assigned to a frame, enabling you to refer to the frame by label instead of by its IDN.

Identification number (IDN)

A unique number assigned to each frame, which you can use to identify the frame when modifying its appearance. Example: if you have defined 3 flow frames, 2 static frames and

1 dynamic frame, the flow frames will have IDNs 1, 2 and 3, the static frames will have IDNs 1 and 2, and the dynamic frame will have IDN 1.

Page list

A list of pages. This can either be a single keyword: `all`, `odd`, `even` or `none`, or it can be a comma-separated list of individual page numbers or page ranges. For example: `<3, 5, 7-11, >15` indicates pages 1,2,5,7,8,9,10,11 and all pages after page 15. These numbers refer to the decimal value of the page counter by default. To make them refer to the absolute page number use the package option `pages=absolute`.

Page range

Page ranges can be closed (for example `5-10`) or open (for example, `<7` or `>9`).












Static frame

Frames in which text is fixed in place. The contents are fixed until explicitly changed or cleared via the `clear` key in `\setstaticcontents`.

Typeblock

The area of the page where the main body of the text goes. The width and height of this area are given by `\typeblockwidth` and `\typeblockheight`. These lengths are initialised to `\textwidth` and `\textheight`, and may be adjusted at the start of the document environment.

A.2. Symbols

Symbol	Description
\mathbb{N}	A counter is being described.
	The syntax and usage of a command, environment or option etc.
	A command, environment or option that is now deprecated.
i	An important message.
	Prominent information.
	L ^A T _E X code to insert into your document.
	The definition of an option value.
	How the example code should appear in the PDF.
	An option that takes a value.
<code>>_</code>	A command-line application invocation that needs to be entered into a terminal or command prompt.
	A boolean option that is initially false.
	A boolean option that is initially true.
	An option that doesn't take a value.
	A warning.

B.1. Command Summary

A

`\adjustcolsep`

flowfram

Adjust the value of `\columnsep` so that it's equal to twice its original value plus `\marginparwidth`. §5; 111

`\afterminitocskip`

initial: `\baselineskip` flowfram

The vertical space after mini-tocs. §6.2; 146

`\appenddfminitoc` $\langle ID \rangle$
(preamble only)

modifier: * flowfram

Appends the mini-toc to the dynamic frame identified by $\langle ID \rangle$ (the IDN for the unstarred version or the IDL for the starred version). The mini-toc support needs to be enabled with `\enableminitoc`. §6.2; 144

`\appenddynamiccontents` $\langle options \rangle$ $\langle ID \rangle$ $\langle content \rangle$

modifier: * flowfram

Appends the given content to the dynamic frames identified by $\langle ID \rangle$, which is the frame's IDN (unstarred) or IDL (starred). If $\langle options \rangle$ is present, they will be applied to the frame at the same time. §2.4; 53

B. Alphabetical Summaries

B.1. Command Summary	191
B.2. Environment Summary	252

B

\beforeminitocskip*initial:* 0pt flowfram

The vertical space before mini-tocs. §6.2; 145

C

\chapter [<toc>] [<thumbtab-title>] { <title> }*modifier:* *

Modified by flowfram, this has an additional optional argument for the thumbtab titles (see [sections-extra-option](#) if you are using a class that also has a second optional argument). Note that the starred version also has both optional arguments.

\chapterfirstpagestyle*initial:* plain flowfram

The page style for the first page of a chapter. §1.6; 33

\ChapterInDynamic { <ID> }*modifier:* * flowfram v2.0+

Adapts \chapter to ensure that chapter titles are placed in the identified dynamic frame. §2.4.1; 54

\cleartoevenpage

flowfram v2.0+

Similar to \cleardoublepage (which clears to the next odd page) this clears to

the next even page for two-sided documents. For one-sided documents this just does `\clearpage`. §2.1.1; 39

`\computebottomedge` { $\langle dim var \rangle$ } flowfram

Computes the position of the bottom edge of the page, relative to the bottom of the typeblock. §4.1; 102

`\computeflowframearea` { $\langle ID list \rangle$ } *modifier:* * flowfram

Computes the minimum area surrounding the listed flow frames (identified by their IDL for the starred version and their IDN for the unstarred version) and stores the results in `\ffareax`, `\ffareay`, `\ffareawidth` and `\ffareaheight`.

`\computeleftedgeeven` { $\langle dim var \rangle$ } flowfram

Computes the position of the leftmost edge of the page, relative to the left side of the typeblock for even pages. §4.1; 101

`\computeleftedgeodd` { $\langle dim var \rangle$ } flowfram

Computes the position of the leftmost edge of the page, relative to the left side of the typeblock for odd pages. §4.1; 101

$$\backslash\texttt{computerightedgeeven}\{\langle dim\ var\rangle\}$$

flowfram

Computes the position of the rightmost edge of the page, relative to the left side of the typeblock for even pages. §4.1; 102

$$\backslash\texttt{computerightedgeodd}\{\langle dim\ var\rangle\}$$

flowfram

Computes the position of the rightmost edge of the page, relative to the left side of the typeblock for odd pages. §4.1; 102

$$\backslash\texttt{computetopedge}\{\langle dim\ var\rangle\}$$

flowfram

Computes the position of the top edge of the page, relative to the bottom of the typeblock. §4.1; 101

$$\backslash\texttt{continueonframe}[\langle text\rangle]\{\langle ID\rangle\}$$


flowfram

Ends the current `staticcontents` or `dynamiccontents` and starts a new environment of the same type for the frame given by $\langle ID \rangle$. If the starred version of the environment was used then $\langle ID \rangle$ refers to the next frame's IDL otherwise it refers to its IDN. If $\langle text \rangle$ is omitted then `\ffdefaultstaticcontinuetext` or `\ffdefault-staticcontinuetext` will be used (with the appropriate arguments), as applicable. §2.3.1; 43

D

\defaultthumtabtype*initial:* varies flowfram

Expands to the default section type to be used by `\makethumtbs` if the `\section-type` argument is missing. The default definition is either `chapter` or `section`, depending on whether or not `\chapter` is defined. §6.1; 138

 **\dfchaphead**{*ID*}*modifier:* * flowfram

Old method for putting chapter title in a dynamic frame.

\dfchapterclearpage

flowfram v2.0+

Used with `\ChapterInDynamic` to start a new page. §2.4.1; 55

\dfEvenFooterStyle{*text*}

flowfram v2.0

Used to format the page footer in the header and footer frame page styles for even pages. §2.4.2; 61

\dfEvenHeaderStyle{*text*}

flowfram v2.0

Used to format the page header in the header and footer frame page styles for even pages. §2.4.2; 61

\dfOddFooterStyle { *⟨text⟩* }

flowfram v2.0

Used to format the page footer in the header and footer frame page styles for odd pages. §2.4.2; 61

\dfOddHeaderStyle { *⟨text⟩* }

flowfram v2.0

Used to format the page header in the header and footer frame page styles for odd pages. §2.4.2; 61

\dfswapoddeven { *⟨ID-list⟩* }

modifier: * flowfram

Swap the odd and even co-ordinates for all listed dynamic frames. §3.1.3; 85

\disablethumbtabs

flowfram

The thumbtab frames created by `\makethumbtabs` will have the `hide` attribute switched on and thumbtab information will stop being written to the `ttb`. §6.1; 140

\dynamicaddexclusion { *⟨IDN⟩* } { *⟨list⟩* }

flowfram v1.14+

Appends *⟨list⟩* to the exclusion list for the dynamic frame identified by its IDN. §3.1.1; 74

\dynamicframeevenx { $\langle IDN \rangle$ }

flowfram

Expands to the even-page x -coordinate of the dynamic frame identified by its IDN. §3.1.3; 82

\dynamicframeeveny { $\langle IDN \rangle$ }

flowfram

Expands to the even-page y -coordinate of the dynamic frame identified by its IDN. §3.1.3; 83

\dynamicframeheight { $\langle IDN \rangle$ }

flowfram

Expands to the height of the dynamic frame identified by its IDN. §3.1.3; 81

\dynamicframewidth { $\langle IDN \rangle$ }

flowfram

Expands to the width of the dynamic frame identified by its IDN. §3.1.3; 80

\dynamicframex { $\langle IDN \rangle$ }

flowfram

Expands to the x -coordinate of the dynamic frame identified by its IDN. §3.1.3; 83

\dynamicframey { $\langle IDN \rangle$ }

flowfram

Expands to the y -coordinate of the dynamic frame identified by its IDN. §3.1.3; 84

\dynamicsetexclusion { *⟨IDN⟩* } { *⟨list⟩* }

flowfram v1.14+

Sets the exclusion list for the dynamic frame identified by its IDN. §3.1.1; 74

\dynamicsetpagelist { *⟨IDN⟩* } { *⟨page-list⟩* | *⟨keyword⟩* } flowfram v1.14+

Sets the page list for the dynamic frame identified by its IDN. §3.1.1; 72

\dynamicswitchoffnext { *⟨ID-list⟩* }

modifier: * flowfram v1.14+

Switch off the listed dynamic frames from the next page onwards. §3.3; 96

\dynamicswitchoffnextodd { *⟨ID-list⟩* }

modifier: * flowfram v1.14+

Switch off the listed dynamic frames from the next odd page onwards (after that they will be off for both even and odd pages). §3.3; 97

\dynamicswitchoffnextoddonly { *⟨ID-list⟩* }

modifier: *

flowfram v1.14+

Switch off the listed dynamic frames for the next odd page only. §3.3; 97

\dynamicsswitchoffnextonly { *⟨ID-list⟩* } *modifier:* *
flowfram v1.14+

Switch off the listed dynamic frames for the next page only. §3.3; 97

\dynamicsswitchonnext { *⟨ID-list⟩* } *modifier:* * flowfram v1.14+

Switch on the listed dynamic frames from the next page onwards. §3.3; 96

\dynamicsswitchonnextodd { *⟨ID-list⟩* } *modifier:* * flowfram v1.14+

Switch on the listed dynamic frames from the next odd page onwards (after that they will show on both even and odd pages). §3.3; 97

\dynamicsswitchonnextoddonly { *⟨ID-list⟩* } *modifier:* *
flowfram v1.14+

Switch on the listed dynamic frames for the next odd page only. §3.3; 97

\dynamicsswitchonnextonly { *⟨ID-list⟩* } *modifier:* * flowfram v1.14+

Switch on the listed dynamic frames for the next page only. §3.3; 97

E

\enableminitoc [*<section-type>*]
(preamble only)

flowfram

Enables mini-tocs at the start of the given sectional unit. §6.2; 144

\enablethumtbs

flowfram

The thumbtab frames created by `\makethumtbs` will have the `hide` attribute switched off and thumbtab information can start being written to the `ttb` file. Any thumbtab sectional units that occur before this command won't have a corresponding thumbtab. §6.1; 139

F

\FFabove

initial: above flowfram v1.11+

Text used to describe one frame is above another. §4.3; 105

\FFaboveleft

initial: above left flowfram v1.11+

Text used to describe one frame above left from another. §4.3; 104

\FFaboveright

initial: above right flowfram v1.11+

Text used to describe one frame above right from another. §4.3; 104

\ffareaheight

flowfram

Used by commands like `\computeflowframearea` to store the calculated height.

\ffareawidth

flowfram

Used by commands like `\computeflowframearea` to store the calculated width.

\ffareax

flowfram

Used by commands like `\computeflowframearea` to store the calculated x position.

\ffareay

flowfram

Used by commands like `\computeflowframearea` to store the calculated y position.

\FFbelow*initial:* below flowfram v1.11+

Text used to describe one frame is below another. §4.3; 105

\FFbelowleft*initial:* below left flowfram v1.11+

Text used to describe one frame below left from another. §4.3; 105

\FFbelowright

initial: below right flowfram v1.11+

Text used to describe one frame below right from another. §4.3; 105

\ffchapterdefaultfont

(only if book or report class)

flowfram v2.0+

The default font declarations for the chapter heading. §2.4.1; 58

\ffchapterheadstyle

(only if book or report class)

flowfram v2.0+

The paragraph style for the chapter header. §2.4.1; 58

\ffchapternum{*<name>*}{*<number>*}

(only if book or report class)

flowfram v2.0+

Typesets the chapter name (Chapter/Appendix) and number. §2.4.1; 59

\ffchapternumfont{*<text>*}

(only if book or report class)

flowfram v2.0+

The font command for the chapter name and number. §2.4.1; 59

\ffchapterpostheadskip

flowfram v2.0+

(only if book or report class)

Vertical space after chapter header. §2.4.1; 58

\ffchapterpostnamenum

flowfram v2.0+

(only if book or report class)

Separator between the chapter number and title. §2.4.1; 59

\ffchapterpreheadskip

flowfram v2.0+

(only if book or report class)

Vertical space before chapter header. §2.4.1; 58

\ffchaptertitlefont { *text* }

flowfram v2.0+

(only if book or report class)

The font command for the chapter title. §2.4.1; 59

\ffcolumnseprule*initial:* 2pt flowfram v1.09+The width/height of the rules created by \insertvrule/\inserthrule. §5.4.4;
132

`\ffcontinuedtextfont` { *⟨text⟩* }

flowfram

Used `\ffcontinuedtextlayout` to apply the font for the continuation text. §2.3.1; 46

`\ffcontinuedtextlayout` { *⟨text⟩* }

flowfram

Used by `\continueonframe` to adjust the current paragraph so that it ends flushed with the right margin and adds the continuation text flush right on the next line. §2.3.1; 46

`\ffdefaultcontinuetext`

initial: *empty* flowfram v2.0+

Default used by both `\ffdefaultstaticcontinuetext` and `\ffdefaultdynamiccontinuetext`. §2.3.1; 46

`\ffdefaultdynamiccontinuetext` { *⟨IDN1⟩* } { *⟨IDN2⟩* }

initial: `\ffdefaultcontinuetext` flowfram v2.0+

Default continuation text if the optional argument of `\continueonframe` is omitted in dynamic frames. The arguments are the IDN of the current frame and of the continuation frame (not the IDL, regardless of the encapsulating command or environment). §2.4.3; 67

`\ffdefaultpostcontinued`

flowfram v2.0+

Default behaviour of `\ffstaticpostcontinued` and `\ffdynamicpostcontinued`. §2.3.1; 48

\ffdefaultstaticcontinuetext { $\langle IDN1 \rangle$ } { $\langle IDN2 \rangle$ }
initial: \ffdefaultcontinuetext flowfram v2.0+

Default continuation text if the optional argument of \continueonframe is omitted in static frames. The arguments are the IDN of the current frame and of the continuation frame (not the IDL, regardless of the encapsulating command or environment). §2.3.1; 45

\ffdynamicpostcontinued { $\langle IDN1 \rangle$ } { $\langle IDN2 \rangle$ }
initial: \ffdefaultpostcontinued flowfram v2.0+

Placed at the start of a dynamic frame with continued content where $\langle IDN1 \rangle$ is the IDN of the previous frame and $\langle IDN2 \rangle$ is the IDN of the continuation frame. §2.4.3; 67

\ffhrule { $\langle offset \rangle$ } { $\langle width \rangle$ } { $\langle height \rangle$ } flowfram v1.11+

Used to draw the rule for \inserthrule. §5.4.4; 134

\fflabelfont flowfram

Font declarations used for the annotation labels shown in draft mode. §7.1; 147

\fflabelsep *initial:* 1pt flowfram

When drawing the bounding boxes in draft mode (but not for the typeblock), this is the distance between the bounding box outline and the label. §7.2; 148

\FFleft*initial:* on the left flowfram v1.11+

Text used to describe one frame is to the left of another. §4.3; 105

\FFoverlap*initial:* overlap flowfram v1.11+

Text used to describe overlapping frames. §4.3; 105

\ffprechapterhook*initial:* empty flowfram v1.14+

Hook added to the start of \chapter. §1.6; 32

\FFright*initial:* on the right flowfram v1.11+

Text used to describe one frame is to the right of another. §4.3; 105

\ffruleddeclarations*initial:* empty flowfram v1.11+

Used by \insertvrule and \inserthrule to apply any declarations that may alter the way that the rule appears. §5.4.4; 133

\ffstaticpostcontinued{*<IDN1>*}{*<IDN2>*}*initial:* \ffdefaultpostcontinued flowfram v2.0+Placed at the start of a static frame with continued content where *<IDN1>* is the IDN of the

previous frame and $\langle IDN2 \rangle$ is the IDN of the continuation frame. §2.3.1; 47

\ffswapoddeven { $\langle ID-list \rangle$ } *modifier:* * flowfram

Swap the odd and even co-ordinates for all listed flow frames. §3.1.3; 84

\fftolerance *initial:* 2pt flowfram v1.14+

The tolerance used when determining whether or not to warn when moving between flow frames of different widths. §2.1.1; 39

\ffvadjustfalse flowfram

Sets the `\ifffvadjust` conditional to false. §5.1; 113

\ffvadjusttrue flowfram

Sets the `\ifffvadjust` conditional to true. §5.1; 114

\ffvrule { $\langle offset \rangle$ } { $\langle width \rangle$ } { $\langle height \rangle$ } flowfram v1.11+

Used to draw the rule for `\insertvrule`. §5.4.4; 133

\finishthispage

flowfram

Similar to the way `\clearpage` works for normal two-column mode, this command issues the correct number of `\newpage` needed to finish the current page to allow a page break even if the current flow frame isn't the last available for the current page. §2.1.1; 39

\FLFsimpar

flowfram v2.0+

Simulate a paragraph break inside `\shapepar` or `\Shapepar`.

\flowaddexclusion { *IDN* } { *list* }

flowfram v1.14+

Appends *list* to the exclusion list for the flow frame identified by its IDN. §3.1.1; 74

\flowfram@doc@htmlopts { *n* } { *key=value*
list } { *type* } { *IDN* } { *page* } { *absolute-page* }

flowfram v2.0+

Does nothing. This command is written to the `aux` file if the `html` option is used in the document environment. It's provided for the benefit of \LaTeX to HTML parsers. §3.1.5; 89

\flowfram@preamble@htmlopts { *n* } { *key=value*
list } { *type* } { *IDN* } { *page* } { *absolute-page* }

flowfram v2.0+

Does nothing. This command is written to the `aux` file if the `html` option is used in the preamble. It's provided for the benefit of \LaTeX to HTML parsers. §3.1.5; 89

`\flowframchapterheader` { *text* }

flowfram v2.0

Used by the `ffheadings` page style to format the chapter mark. §2.4.2; 61

`\flowframeevenx` { *IDN* }

flowfram

Expands to the even-page *x*-coordinate of the flow frame identified by its IDN. §3.1.3; 82

`\flowframeeveny` { *IDN* }

flowfram

Expands to the even-page *y*-coordinate of the flow frame identified by its IDN. §3.1.3; 82

`\flowframeheight` { *IDN* }

flowfram

Expands to the height of the flow frame identified by its IDN. §3.1.3; 80

`\flowframerule`

flowfram

The width of the rule for the border of frames, if the standard border is used. This is initialised to `\fboxrule` when flowfram loads. §7.2; 148

`\flowframesep`

flowfram

The gap between the text and the border of frames, if the standard border is used. This is initialised to `\fboxsep` when flowfram loads. §7.2; 148

\flowframeshowlayout

flowfram

Finishes the current page, temporarily sets draft mode, and prints an empty page. §1.4; 30

\flowframewidth{ *IDN* }

flowfram

Expands to the width of the flow frame identified by its IDN. §3.1.3; 80

\flowframex{ *IDN* }

flowfram

Expands to the *x*-coordinate of the flow frame identified by its IDN. §3.1.3; 83

\flowframey{ *IDN* }

flowfram

Expands to the *y*-coordinate of the flow frame identified by its IDN. §3.1.3; 84

\flowframheaderchapprefix

initial: varies flowfram v2.0

Prefix inserted before the chapter number. §2.4.2; 62

\flowframheadersep

initial: varies flowfram v2.0

Separator used between the chapter or section number and the title (when the number is shown). §2.4.2; 62

\FlowFramRestoreOR
(not preamble)

flowfram v2.0+

Restore the original output routine (the current page will be finished and output first). §1.5; 31

\flowframsectionheader { *text* }

flowfram v2.0

Used by the `ffheadings` page style to format the section mark. §2.4.2; 62

\flowframsetup { *key=value list* }

flowfram v2.0+

Set any options that may be adjusted after the package has loaded. §1.2; 10

\flowframsubsectionheader { *text* }

flowfram v2.0

Used by the `ffheadings` page style to format the subsection mark.

\FlowframTkBeginScopeIfGroup { *class name* }

flowframtkutils v2.2+

Designed for use in the definition of `\flowframtkstartobject`, this command will insert `\begin{pgfscope}` if *class name* is `JDRGroup`, otherwise it will do nothing. §8.4.2; 163

\flowframtkencapobject { $\langle n \rangle$ } { $\langle \text{Java class name} \rangle$ } { $\langle \text{description} \rangle$ } { $\langle \text{tag} \rangle$ } { $\langle \text{pgf point} \rangle$ } { $\langle \text{width} \rangle$ } { $\langle \text{height} \rangle$ } { $\langle \text{object} \rangle$ }
flowframtkutils v2.0+

Encapsulates an object that forms part of an image. §8.4.2; 161

\flowframtkendobject { $\langle n \rangle$ } { $\langle \text{Java class name} \rangle$ } { $\langle \text{description} \rangle$ } { $\langle \text{tag} \rangle$ } { $\langle \text{pgf point} \rangle$ } { $\langle \text{width} \rangle$ } { $\langle \text{height} \rangle$ }
flowframtkutils v2.0+

Marks the end of an object that forms part of the image. Should always be paired with a matching \flowframtkstartobject. §8.4.2; 161

\FlowframTkEndScopeIfGroup { $\langle \text{class name} \rangle$ } flowframtkutils v2.2+

Designed for use in the definition of \flowframtkendobject, this command will insert \end{pgfscope} if $\langle \text{class name} \rangle$ is JDRGroup, otherwise it will do nothing. §8.4.2; 163

\flowframtkimageinfo { $\langle \text{key=value list} \rangle$ } flowframtkutils v2.0+

Set the document title and creation date. §8.4.2; 159

\flowframtkimgtitlechar { *⟨char⟩* } { *⟨PDF replacement⟩* }

flowframtkutils v2.0+

Normally just expands to *⟨char⟩*. §8.4.2; 160

\flowframtkNoRagged

flowframtkutils v2.2+

Restores paragraph justification back to the state it was in when flowframtkutils was loaded. §8.4.2; 160

\FlowframTkScopeIfGroup { *⟨class name⟩* } { *⟨object⟩* }

flowframtkutils v2.2+

Designed for use in the definition of `\flowframtkencapobject`, this command will encapsulate *⟨object⟩* within the `pgfscope` environment if *⟨class name⟩* is `JDRGroup`, otherwise it will just do *⟨object⟩*. §8.4.2; 164

\flowframtkSetCreationDate { *⟨PDF date⟩* }

flowframtkutils v2.0+

Set the PDF creation date. §8.4.2; 159

\flowframtkSetTitle { *⟨title⟩* }

flowframtkutils v2.0+

Set the document title. §8.4.2; 159

\flowframtkstartobject { $\langle n \rangle$ } { $\langle \text{Java class name} \rangle$ } { $\langle \text{description} \rangle$ } { $\langle \text{tag} \rangle$ } { $\langle \text{pgf point} \rangle$ } { $\langle \text{width} \rangle$ } { $\langle \text{height} \rangle$ }
 flowframtkutils v2.0+

Marks the start of an object that forms part of the image. Should always be paired with a matching `\flowframtkendobject`. §8.4.2; 161

\FlowFramTkUtilsOverlayEncapSetup { $\langle \text{key=value list} \rangle$ }
 flowframtkutils v2.0+

Set the options for `\FlowFramTkUtilsSetOverlayEncap`. §8.4.2; 165

\FlowFramTkUtilsSetOverlayEncap [$\langle \text{key=value list} \rangle$]
 flowframtkutils v2.0+

Redefines `\flowframtkencapobject` to use a low-level command (`\flowframtkutils_uncover_encap:nnnnnnnn`) that uncovers objects according to the settings given in the optional argument. The settings may be changed later with `\FlowFramTkUtilsOverlayEncapSetup`. §8.4.2; 164

\flowframtkutils_uncover_encap:nnnnnnnn { $\langle n \rangle$ }
 { $\langle \text{Java class name} \rangle$ } { $\langle \text{description} \rangle$ } { $\langle \text{tag} \rangle$ } { $\langle \text{pgf point} \rangle$ } { $\langle \text{width} \rangle$ }
 { $\langle \text{height} \rangle$ } { $\langle \text{object} \rangle$ } flowframtkutils v2.0+

The low-level function used by `\flowframtkencapobject` when enabled with `\FlowFramTkUtilsSetOverlayEncap`. §8.4.2; 164

\flowframtkutils_uncover_from:nn {*number*} {*content*}
flowframtkutils v2.0+

Used by \flowframtkutils_uncover_encap:nnnnnnnn to uncover an object from *number*. §8.4.2; 165

\flowframtkutils_uncover:nn {*number*} {*content*}
flowframtkutils v2.0+

Used by \flowframtkutils_uncover_encap:nnnnnnnn to uncover an object on a single overlay. §8.4.2; 165

\FlowFramUnrestoreOR flowfram v2.0+
(not preamble)

Restore flowfram's modified output routine (the current page will be finished and output first). §1.5; 32

\flowsetexclusion{*IDN*}{*list*} flowfram v1.14+

Sets the exclusion list for the flow frame identified by its IDN. §3.1.1; 74

\flowsetpagelist{*IDN*}{*page-list* | *keyword*} flowfram v1.14+

Sets the page list for the flow frame identified by its IDN. §3.1.1; 72

\flowswitchoffnext { *⟨ID-list⟩* }

modifier: * flowfram v1.14+

Switch off the listed flow frames from the next page onwards. §3.3; 95

\flowswitchoffnextodd { *⟨ID-list⟩* }

modifier: * flowfram v1.14+

Switch off the listed flow frames from the next odd page onwards (after that they will be off for both even and odd pages). §3.3; 96

\flowswitchoffnextoddonly { *⟨ID-list⟩* }

modifier: *

flowfram v1.14+

Switch off the listed flow frames for the next odd page only. §3.3; 96

\flowswitchoffnextonly { *⟨ID-list⟩* }

modifier: * flowfram v1.14+

Switch off the listed flow frames for the next page only. §3.3; 96

\flowswitchonnext { *⟨ID-list⟩* }

modifier: * flowfram v1.14+

Switch on the listed flow frames from the next page onwards. §3.3; 95

\flowswitchonnextodd { *⟨ID-list⟩* }

modifier: * flowfram v1.14+

Switch on the listed flow frames from the next odd page onwards (after that they will show

on both even and odd pages). §3.3; 95

\flowswitchonnextoddone { $\langle ID\text{-list} \rangle$ } *modifier:* * flowfram v1.14+

Switch on the listed flow frames for the next odd page only. §3.3; 96

\flowswitchonnextonly { $\langle ID\text{-list} \rangle$ } *modifier:* * flowfram v1.14+

Switch on the listed flow frames for the next page only. §3.3; 96

\framebreak [$\langle n \rangle$] flowfram

Forces a break from one frame to another. This creates a paragraph break in order to ensure the output routine adjusts to the new frame width but gives the effect of a continuous paragraph (although this may cause excess spacing). §2.1.1; 38

G

\getdynamicbounds { $\langle ID \rangle$ } *modifier:* * flowfram

Gets the bounds for the dynamic frame identified by $\langle ID \rangle$ (the IDL for the starred version and the IDN for the unstarred version) and stores the results in `\ffareax`, `\ffareay`, `\ffareawidth` and `\ffareaheight`. §4.2; 103

\getdynamicid{*⟨cmd⟩*}{*⟨IDL⟩*}

flowfram v1.11+

Defines the command *⟨cmd⟩* to expand to the IDN of the dynamic frame identified by its IDL. §2.4; 52

\getdynamiclabel{*⟨IDN⟩*}

flowfram v1.11+

Expands to the IDL of the dynamic frame identified by its IDN. §2.4; 51

\getflowbounds{*⟨ID⟩*}

modifier: * flowfram

Gets the bounds for the flow frame identified by *⟨ID⟩* (the IDL for the starred version and the IDN for the unstarred version) and stores the results in `\ffareax`, `\ffareay`, `\ffareawidth` and `\ffareaheight`. §4.2; 103

\getflowid{*⟨cmd⟩*}{*⟨IDL⟩*}

flowfram v1.11+

Defines the command *⟨cmd⟩* to expand to the IDN of the flow frame identified by its IDL. §2.1; 37

\getflowlabel{*⟨IDN⟩*}

flowfram v1.11+

Expands to the IDL of the flow frame identified by its IDN. §2.1; 36

\getstaticbounds { *ID* }*modifier:* * flowfram

Gets the bounds for the static frame identified by *ID* (the IDL for the starred version and the IDN for the unstarred version) and stores the results in `\ffareax`, `\ffareay`, `\ffareawidth` and `\ffareaheight`. §4.2; 103

\getstaticid { *cmd* } { *IDL* }

flowfram v1.11+

Defines the command *cmd* to expand to the IDN of the static frame identified by its IDL. §2.2; 41

\getstaticlabel { *IDN* }

flowfram v1.11+

Expands to the IDL of the static frame identified by its IDN. §2.2; 41

H

\hNtone [*page-list*] [*y-offset*] { *n* } { *HI* } { *CI* } { *LI* } ... { *Hn* }
 { *Cn* } { *Ln* }

flowfram

As `\htwotone` but creates *n* static frames. §5.4.2; 130

```
\hNtoneleft [⟨page-list⟩] [⟨y-offset⟩] {⟨n⟩} {⟨W⟩} {⟨H1⟩} {⟨C1⟩}
{⟨L1⟩}...{⟨Hn⟩} {⟨Cn⟩} {⟨Ln⟩} flowfram
```

As `\htwotoneleft` but creates $\langle n \rangle$ static frames. §5.4.2; 131

```
\hNtoneright [⟨page-list⟩] [⟨y-offset⟩] {⟨n⟩} {⟨W⟩} {⟨H1⟩} {⟨C1⟩}
{⟨L1⟩}...{⟨Hn⟩} {⟨Cn⟩} {⟨Ln⟩} flowfram
```

As `\htwotoneright` but creates $\langle n \rangle$ static frames. §5.4.2; 131

```
\htwotone [⟨page-list⟩] [⟨y-offset⟩] {⟨H1⟩} {⟨C1⟩} {⟨L1⟩} {⟨H2⟩} {⟨C2⟩}
{⟨L2⟩} flowfram
```

Defines two vertically stacked static frames where the first frame has height $\langle H1 \rangle$, background colour $\langle C1 \rangle$ and label $\langle L1 \rangle$, and the second frame has height $\langle H2 \rangle$, background colour $\langle C1 \rangle$ and label $\langle L2 \rangle$. Both frames have the width set to `\paperwidth` and are positioned so that their left edge is at the left side of the page, with the first frame offset from the bottom edge of the page by $\langle y\text{-offset} \rangle$. Note that the colour specifications $\langle C1 \rangle$ and $\langle C2 \rangle$ should be enclosed in braces, for example `{[gray]{0.5}}` not `[gray]{0.5}`. §5.4.2; 130

```
\htwotoneleft [⟨page-list⟩] [⟨y-offset⟩] {⟨W⟩} {⟨H1⟩} {⟨C1⟩} {⟨L1⟩}
{⟨H2⟩} {⟨C2⟩} {⟨L2⟩} flowfram
```

As `\htwotone` but instead of being the full width of the page, the width for both frames is set to $\langle W \rangle$. §5.4.2; 130

```
\htwotoneright [<page-list>] [<y-offset>] {<W>} {<H1>} {<C1>} {<L1>}  
{<H2>} {<C2>} {<L2>} flowfram
```

As `\htwotoneleft` but horizontally offset so that the right edge of the frames is along the right edge of the page. §5.4.2; 131

I

```
\iffvadjust <true>\else <false>\fi initial: \iftrue flowfram
```

If true, the column commands, such as `\onecolumninarea` will adjust the specified height to ensure that it is an integer multiple of `\baselineskip`. §5.1; 114

```
\iflefttorightcolumns <true>\else <false>\fi  
initial: \iftrue flowfram v1.12+
```

Set to `\iftrue` by the `LR` package option and to `\iffalse` by the `RL` option, this conditional determines the order of frames created by the column commands, such as `\twocolumn`. §5.3; 127

```
\IfSavedRelativeLocationAbove {<label>} {<true>} {<false>}  
flowfram v2.0+
```

Tests if the saved result from `\SaveRelativeFrameLocation` indicates that the first frame is above the second frame, without regard to their horizontal positions. §4.3; 109

\IfSavedRelativeLocationBelow { *⟨label⟩* } { *⟨true⟩* } { *⟨false⟩* }

flowfram v2.0+

Tests if the saved result from `\SaveRelativeFrameLocation` indicates that the first frame is below the second frame, without regard to their horizontal positions. §4.3; 109

\IfSavedRelativeLocationEq { *⟨label⟩* } { *⟨cmd⟩* } { *⟨true⟩* } { *⟨false⟩* }

flowfram v2.0+

Tests if the saved result from `\SaveRelativeFrameLocation` matches *⟨cmd⟩*, which should be one of the relative placeholder commands such as `\FFabove`. §4.3; 108

\IfSavedRelativeLocationLeft { *⟨label⟩* } { *⟨true⟩* } { *⟨false⟩* }

flowfram v2.0+

Tests if the saved result from `\SaveRelativeFrameLocation` indicates that the first frame is left of the second frame, without regard to their vertical positions. §4.3; 109

\IfSavedRelativeLocationRight { *⟨label⟩* } { *⟨true⟩* } { *⟨false⟩* }

flowfram v2.0+

Tests if the saved result from `\SaveRelativeFrameLocation` indicates that the first frame is right of the second frame, without regard to their vertical positions. §4.3; 109

```
\ifshowframebbox  $\langle true \rangle$  \else  $\langle false \rangle$  \fi    initial: \iffalse  
flowfram
```

If true, the bounding boxes of all frames will be drawn in grey on the page. §1.4; 30

```
\ifshowmargins  $\langle true \rangle$  \else  $\langle false \rangle$  \fi    initial: \iffalse  
flowfram
```

If true, the flow frame margins will be drawn in grey on the page. §1.4; 29

```
\ifshowtypeblock  $\langle true \rangle$  \else  $\langle false \rangle$  \fi    initial: \iffalse  
flowfram
```

If true, the typeblock will be drawn in grey on the page. §1.4; 29

```
\includeteximage [ $\langle key=value list \rangle$ ] {  $\langle filename \rangle$  }    flowframtkutils v2.0+
```

If the optional argument is omitted, this just inputs $\langle filename \rangle$, otherwise it applies a transformation according to the options. §8.4.2; 157

```
\inserthrule [ $\langle x-left \rangle$ ] [ $\langle x-right \rangle$ ] {  $\langle type-1 \rangle$  } {  $\langle ID1 \rangle$  } {  $\langle type-2 \rangle$  }  
{  $\langle ID2 \rangle$  }    modifier: *    flowfram
```

Creates a horizontal rule between two frames. The starred version references the frames by their IDL otherwise the frames are referenced by their IDN. The rule will extend from the

leftmost point of the two frames minus $\langle x\text{-left} \rangle$ to the rightmost point of the two frames plus $\langle x\text{-right} \rangle$. §5.4.4; 133

`\insertvrule` [$\langle y\text{-top} \rangle$] [$\langle y\text{-bottom} \rangle$] { $\langle type\text{-1} \rangle$ } { $\langle ID1 \rangle$ } { $\langle type\text{-2} \rangle$ }
 { $\langle ID2 \rangle$ } modifier: * flowfram

Creates a vertical rule between two frames. The starred version references the frames by their IDL otherwise the frames are referenced by their IDN. The rule will extend from the highest point of the two frames plus $\langle y\text{-top} \rangle$ to the lowest point of the two frames minus $\langle y\text{-bottom} \rangle$. §5.4.4; 132

J

`\jdrimagebox` { $\langle image \rangle$ } flowframkutils

Used for encapsulated images, this is designed to prevent problems if numerical rounding errors cause the image to be larger than the available area. §8.4.2; 158

`\jdroutline` { $\langle pdf\text{-trans code} \rangle$ } { $\langle pst\text{-char code} \rangle$ } { $\langle text \rangle$ } flowframkutils

If enabled by the `outline` option, this will attempt to render $\langle text \rangle$ as an outline using $\langle pdf\text{-trans code} \rangle$ (if `pdf-trans.tex` was loaded) or $\langle pst\text{-char code} \rangle$ (if `pst-char` was loaded). If not enabled, this command will generate a warning and just do $\langle text \rangle$. §8.4.2; 158

L

\labelflow{*⟨label⟩*}

flowfram v1.11+

Labels the current flow frame with `\label` so that its displayed index (`displayedframe`) can be referenced with `\ref`. §7.3; 151

\labelflowidn{*⟨label⟩*}

flowfram v1.11+

Labels the current flow frame with `\label` so that its IDN can be referenced with `\ref`. §7.3; 150

\lefttorightcolumnsfalse

flowfram v1.12+

Sets the `\iflefttorightcolumns` conditional to false. §5.3; 127

\lefttorightcolumnstrue

flowfram v1.12+

Sets the `\iflefttorightcolumns` conditional to true. §5.3; 127

M

\makebackgroundframe[*⟨page-list⟩*][*⟨label⟩*]

flowfram

Creates a single static frame that covers the entire page. This command, if required, should come before any other static frames that are shown on any of the pages in *⟨page-list⟩* otherwise it will obscure them. §5.4.3; 131

\makedfheaderfooter
(preamble only)

flowfram

Creates the header and footer dynamic frames to use for the page header and footer. They can then be moved, resized or styled as required. This command will set the `ffheadings` package style and, depending on the `dynamic-page-style` setting, may adjust the standard page styles. §2.4.2; 60

\makethumtbs [$\langle y\text{-offset} \rangle$] { $\langle height \rangle$ } [$\langle section\text{-type} \rangle$]
(preamble only)

flowfram

Create thumbtabs for the given section type with the given height, where the first thumbtab is offset from the top of the typeblock by $\langle y\text{-offset} \rangle$. This command first inputs the `ttb` file to read the information from the previous run and then opens the file to allow information from this run to be written to it. Note that the thumbtab dynamic frames will have the `hide` attribute switched on. This will be switched off by `\enablethumtbs`. §6.1; 137

\minitocstyle { $\langle content \rangle$ }

flowfram

The style used to format the mini-toc. §6.2; 145

N

\Ncolumn [$\langle page\text{-list} \rangle$] { $\langle n \rangle$ } [$\langle label \rangle$]

(preamble only)

Creates $\langle n \rangle$ flow frames that fit in the typeblock separated by the distance given by `\column-`

sep, with the height adjusted if the conditional `\iffvadjust` is true. §5.1; 114

`\Ncolumnbottom` [*page-list*] {*type*} {*n*} {*top-height*} [*label*]

flowfram

(preamble only)

As `\Ncolumnbottominarea` where the area is given by the `typeblock`. §5.2; 125

`\Ncolumnbottominarea` [*page-list*] {*type*} {*n*} {*top-height*}

{*width*} {*height*} {*x*} {*y*} [*label*]

flowfram

(preamble only)

Creates a frame of the given type (flow, static or dynamic) and height *top-height* and *n* side-by-side flow frames that all fit in the given area such that the first frame is below the other *n* frames, separated by `\vcolumnsep`. The height of the *n* side-by-side flow frames is adjusted if `\iffvadjust` is true. The horizontal gap between them is given by `\columnsep`. §5.2; 117

`\NcolumnDbottom` [*page-list*] {*n*} {*top-height*} [*label*]

flowfram

(preamble only)

As `\Ncolumnbottom` with the *type* set to `dynamic`. §5.2; 126

\NcolumnDbottominarea [*⟨page-list⟩*] {*⟨n⟩*} {*⟨bottom-height⟩*}
 {*⟨width⟩*} {*⟨height⟩*} {*⟨x⟩*} {*⟨y⟩*} [*⟨label⟩*] flowfram
 (preamble only)

As \Ncolumnbottominarea with the *⟨type⟩* set to dynamic. §5.2; 125

\NcolumnDtop [*⟨page-list⟩*] {*⟨n⟩*} {*⟨top-height⟩*} [*⟨label⟩*] flowfram
 (preamble only)

As \Ncolumnntop with the *⟨type⟩* set to dynamic. §5.2; 121

\NcolumnDtopinarea [*⟨page-list⟩*] {*⟨n⟩*} {*⟨top-height⟩*} {*⟨width⟩*}
 {*⟨height⟩*} {*⟨x⟩*} {*⟨y⟩*} [*⟨label⟩*] flowfram
 (preamble only)

As \Ncolumnntopinarea with the *⟨type⟩* set to dynamic. §5.2; 121

\Ncolumninarea [*⟨page-list⟩*] {*⟨n⟩*} {*⟨width⟩*} {*⟨height⟩*} {*⟨x⟩*} {*⟨y⟩*}
 [*⟨labels⟩*] flowfram
 (preamble only)

Creates *⟨n⟩* flow frames that span the given area separated by the distance given by \columnsep, with the height adjusted if the conditional \iffvadjust is true. §5.1; 115

\NcolumnSbottom [*⟨page-list⟩*] {*⟨n⟩*} {*⟨top-height⟩*} [*⟨label⟩*] flowfram
(preamble only)

As \Ncolumnbottom with the *⟨type⟩* set to static. §5.2; 126

\NcolumnSbottominarea [*⟨page-list⟩*] {*⟨n⟩*} {*⟨bottom-height⟩*}
{*⟨width⟩*} {*⟨height⟩*} {*⟨x⟩*} {*⟨y⟩*} [*⟨label⟩*] flowfram
(preamble only)

As \Ncolumnbottominarea with the *⟨type⟩* set to static. §5.2; 125

\NcolumnStop [*⟨page-list⟩*] {*⟨n⟩*} {*⟨top-height⟩*} [*⟨label⟩*] flowfram
(preamble only)

As \Ncolumnstop with the *⟨type⟩* set to static. §5.2; 121

\NcolumnStopinarea [*⟨page-list⟩*] {*⟨n⟩*} {*⟨top-height⟩*} {*⟨width⟩*}
{*⟨height⟩*} {*⟨x⟩*} {*⟨y⟩*} [*⟨label⟩*] flowfram
(preamble only)

As \Ncolumnstopinarea with the *⟨type⟩* set to static. §5.2; 120

\Ncolumnstop [*⟨page-list⟩*] {*⟨type⟩*} {*⟨n⟩*} {*⟨top-height⟩*} [*⟨label⟩*] flowfram
(preamble only)

As \Ncolumnstopinarea where the area is given by the typeblock. §5.2; 121

\Ncolumntopinarea [*<page-list>*] { *<type>* } { *<n>* } { *<top-height>* }
 { *<width>* } { *<height>* } { *<x>* } { *<y>* } [*<label>*] flowfram
 (preamble only)

Creates a frame of the given type (flow, static or dynamic) and height *<top-height>* and *<n>* side-by-side flow frames that all fit in the given area such that the first frame is above the other *<n>* frames, separated by `\vcolumnsep`. The height of the *<n>* side-by-side flow frames is adjusted if `\iffvadjust` is true. The horizontal gap between them is given by `\columnsep`. §5.2; 116

\newdynamicframe [*<page-list>*] { *<width>* } { *<height>* } { *<x>* } { *<y>* }
 [*<label>*] *modifier*: * flowfram
 (preamble only)

Defines a new dynamic frame with the given dimensions and location. If *<label>* is provided, that will be set as the frame's IDL otherwise the IDL will be the same as the IDN. §2.4; 51

\newflowframe [*<page-list>*] { *<width>* } { *<height>* } { *<x>* } { *<y>* } [*<label>*]
modifier: * flowfram
 (preamble only)

Defines a new flow frame with the given dimensions and location. If *<label>* is provided, that will be set as the frame's IDL otherwise the IDL will be the same as the IDN. §2.1; 35

```
\newframe [ <page-list> ] { <frame-type> } { <width> } { <height> } { <x> } { <y> }
[ <label> ] modifier: * flowfram
(preamble only)
```

Defines a new frame of the given *<frame-type>* with the given dimensions and location. If *<label>* is provided, that will be set as the frame's IDL otherwise the IDL will be the same as the IDN. §5.2; 126

```
\newstaticframe [ <page-list> ] { <width> } { <height> } { <x> } { <y> }
[ <label> ] modifier: * flowfram
(preamble only)
```

Defines a new static frame with the given dimensions and location. If *<label>* is provided, that will be set as the frame's IDL otherwise the IDL will be the same as the IDN. §2.2; 40

O

```
\onecolumn [ <page-list> ] [ <label> ] (redefined by flowfram)
```

Creates a flow frame that spans the typeblock, with the height adjusted if the conditional `\iffvadjust` is true. §5.1; 112

\onecolumnbottom [*<page-list>*] { *<type>* } { *<bottom-height>* } [*<label>*]

flowfram

(preamble only)

As `\onecolumnbottominarea` where the area is given by the typeblock. §5.2; 122

\onecolumnbottominarea [*<page-list>*] { *<type>* } { *<bottom-height>* }

{ *<width>* } { *<height>* } { *<x>* } { *<y>* } [*<label>*]

flowfram

(preamble only)

Creates a frame of the given type (flow, static or dynamic) and height *<bottom-height>* and a flow frame that fit in the given area so that the first frame is below the second frame, separated by `\vcolumnsep`. The height of the second frame is adjusted if `\iffvadjust` is true. §5.2; 116

\onecolumnDbottom [*<page-list>*] { *<bottom-height>* } [*<label>*]

flowfram

(preamble only)

As `\onecolumnbottom` with the *<type>* set to dynamic. §5.2; 123

\onecolumnDbottominarea [*<page-list>*] { *<bottom-height>* } { *<width>* }

{ *<height>* } { *<x>* } { *<y>* } [*<label>*]

flowfram

(preamble only)

As `\onecolumnbottominarea` with the *<type>* set to dynamic. §5.2; 122

\onecolumnDtop [*<page-list>*] { *<top-height>* } [*<label>*] flowfram
(preamble only)

As `\onecolumnDtop` with the *<type>* set to `dynamic`. §5.2; 118

\onecolumnDtopinarea [*<page-list>*] { *<top-height>* } { *<width>* }
{ *<height>* } { *<x>* } { *<y>* } [*<label>*] flowfram
(preamble only)

As `\onecolumnDtopinarea` with the *<type>* set to `dynamic`. §5.2; 118

\onecolumninarea [*<page-list>*] { *<width>* } { *<height>* } { *<x>* } { *<y>* }
[*<label>*] flowfram
(preamble only)

Creates a flow frame that spans the given area, with the height adjusted if the conditional `\iffvadjust` is true. §5.1; 114

\onecolumnSbottom [*<page-list>*] { *<bottom-height>* } [*<label>*] flowfram
(preamble only)

As `\onecolumnSbottom` with the *<type>* set to `static`. §5.2; 123

\onecolumnSbottominarea [*<page-list>*] {*<bottom-height>*} {*<width>*}
 {*<height>*} {*<x>*} {*<y>*} [*<label>*] flowfram
 (preamble only)

As `\onecolumnbottominarea` with the *<type>* set to `static`. §5.2; 122

\onecolumnStop [*<page-list>*] {*<top-height>*} [*<label>*] flowfram
 (preamble only)

As `\onecolumnntop` with the *<type>* set to `static`. §5.2; 118

\onecolumnStopinarea [*<page-list>*] {*<top-height>*} {*<width>*}
 {*<height>*} {*<x>*} {*<y>*} [*<label>*] flowfram
 (preamble only)

As `\onecolumnntopinarea` with the *<type>* set to `static`. §5.2; 117

\onecolumnntop [*<page-list>*] {*<type>*} {*<top-height>*} [*<label>*] flowfram
 (preamble only)

As `\onecolumnntopinarea` where the area is given by the `typeblock`. §5.2; 118

\onecolumntopinarea [*<page-list>*] { *<type>* } { *<top-height>* } { *<width>* }
 { *<height>* } { *<x>* } { *<y>* } [*<label>*] flowfram
 (preamble only)

Creates a frame of the given type (flow, static or dynamic) and height *<top-height>* and a flow frame that fit in the given area so that the first frame is above the second frame, separated by `\vcolumnsep`. The height of the second frame is adjusted if `\iffvadjust` is true. §5.2; 116

P

\part [*<toc>*] [*<thumbtab-title>*] { *<title>* } *modifier: **

Modified by `flowfram`, this has an additional optional argument for the thumbtab titles (see `sections-extra-option` if you are using a class that also has a second optional argument). Note that the starred version also has both optional arguments.

R

\RefSavedRelativeLocation { *<label>* } flowfram v2.0+

Fetches the information saved on the previous run with `\SaveRelativeFrameLocation`. §4.3; 108

\relativeframelocation { $\langle type1 \rangle$ } { $\langle ID1 \rangle$ } { $\langle type2 \rangle$ } { $\langle ID2 \rangle$ }
modifier: * flowfram v1.11+

Produces a textual description of the relative location of the $\langle type1 \rangle$ frame identified by $\langle ID1 \rangle$ to the $\langle type2 \rangle$ frame identified by $\langle ID2 \rangle$ (the starred version references the frames by their IDL and the unstarred version references them by their IDN). §4.3; 104

\reldynamicloc { $\langle ID1 \rangle$ } { $\langle ID2 \rangle$ } *modifier:* * flowfram v1.11+

Shortcut for \relativeframelocation where both frame types are dynamic. §4.3; 106

\relflowloc { $\langle ID1 \rangle$ } { $\langle ID2 \rangle$ } *modifier:* * flowfram v1.11+

Shortcut for \relativeframelocation where both frame types are flow. §4.3; 107

\relstaticloc { $\langle ID1 \rangle$ } { $\langle ID2 \rangle$ } *modifier:* * flowfram v1.11+

Shortcut for \relativeframelocation where both frame types are static. §4.3; 106

S

\SaveRelativeFrameLocation { $\langle label \rangle$ } { $\langle type1 \rangle$ } { $\langle ID1 \rangle$ }
 { $\langle type2 \rangle$ } { $\langle ID2 \rangle$ } *modifier:* * flowfram v2.0+

Similar to `\relativeframelocation` but defers the calculations for the next \LaTeX run. The result may be referenced with `\RefSavedRelativeLocation`.
[§4.3](#); 107

\sdfparindent *initial:* 0pt flowfram

The default paragraph indentation within static and dynamic frames (may be overridden for individual frames through the `parindent` option). [§7.2](#); 148

\section [$\langle toc \rangle$] [$\langle thumbtab-title \rangle$] { $\langle title \rangle$ } *modifier:* *

Modified by `flowfram`, this has an additional optional argument for the thumbtab titles (see [sections-extra-option](#) if you are using a class that also has a second optional argument). Note that the starred version also has both optional arguments.

\setalldynamicframes { $\langle key=value list \rangle$ } flowfram

Sets the attributes in $\langle\langle key=value list \rangle\rangle$ for all defined dynamic frames. [§3](#); 70

\setallflowframes { $\langle key=value list \rangle$ } flowfram

Sets the attributes in $\langle\langle key=value list \rangle\rangle$ for all defined flow frames. [§3](#); 69

\setallstaticframes { $\langle key=value list \rangle$ }

flowfram

Sets the attributes in $\langle\langle key=value list \rangle\rangle$ for all defined static frames. §3; 69

\setdynamiccontents [options] { $\langle ID \rangle$ } { $\langle content \rangle$ } *modifier:* *

flowfram

Sets the content of the dynamic frames identified by $\langle ID \rangle$, which is the frame's IDN (unstarred) or IDL (starred). If $\langle options \rangle$ is present, they will be applied to the frame at the same time. §2.4; 52

\setdynamicframe { $\langle ID-list \rangle$ } { $\langle key=value list \rangle$ } *modifier:* * flowfram

Sets the attributes for the given dynamic frames, identified by the list of IDs, which each identify a frame by its IDN (unstarred) or IDL (starred). §3; 70

\setffdraftcolor

flowfram

Sets the colour of the bounding box outlines in draft mode. §7.1; 147

\setffdrafttypeblockcolor

flowfram

Sets the colour of the typeblock outline in draft mode. §7.1; 147

\setflowframe { *ID-list* } { *key=value list* } *modifier:* * flowfram

Sets the attributes for the given flow frames, identified by the list of IDs, which each identify a frame by its IDN (unstarred) or IDL (starred). §3; 69

\SetOneColumnFrame { *ID* } *modifier:* * flowfram v2.0+

For use with `column-changes=switch`, this command identifies the flow frame to use if `\onecolumn` is encountered in the document environment. §1.2.3; 23

\setstaticcontents [*options*] { *ID* } { *content* } *modifier:* *
flowfram

Sets the content of the given static frames identified by *ID*, which is the frame's IDN (unstarred) or IDL (starred). If *options* is present, they will be applied to the frame at the same time. §2.3; 42

\setstaticframe { *ID-list* } { *key=value list* } *modifier:* * flowfram

Sets the attributes for the given static frames, identified by the list of IDs, which each identify a frame by its IDN (unstarred) or IDL (starred). §3; 69

\setthumtab { *index* | `all` } { *key=value list* } flowfram

Sets the given attributes for all of the dynamic frames for the thumtab with the identified index or for all thumtaps if the first argument is the keyword `all`. §6.1; 142

`\setthumtabindex` { *`<index>`* | `all` } { *`<key=value list>`* } flowfram

Sets the given attributes for the thumtab index frame with the identified index or for all thumbtabs index frames if the first argument is the keyword `all`. §6.1; 142

`\SetTwoColumnFrames` [*`<header-type>`*] [*`<header-id>`*] { *`<col-1>`* }
[*`<header-col1>`*] { *`<col-2>`* } [*`<header-col-2>`*] *modifier:* * flowfram v2.0+

For use with `column-changes=switch`, this command identifies the frames to use if `\twocolumn` is encountered in the document environment. §1.2.3; 24

`\sfswapoddeven` { *`<ID-list>`* } *modifier:* * flowfram

Swap the odd and even co-ordinates for all listed static frames. §3.1.3; 85

`\showframebboxfalse` flowfram

Sets the `\ifshowframebbox` conditional to false. §1.4; 30

`\showframebboxtrue` flowfram

Sets the `\ifshowframebbox` conditional to true. §1.4; 30

\showmarginsfalse

flowfram

Sets the `\ifshowmargins` conditional to false. §1.4; 30

\showmarginstrue

flowfram

Sets the `\ifshowmargins` conditional to true. §1.4; 30

\showtypeblockfalse


flowfram

Sets the `\ifshowtypeblock` conditional to false. §1.4; 29

\showtypeblocktrue

flowfram

Sets the `\ifshowtypeblock` conditional to true. §1.4; 29

 **\simpar**

flowfram

Old name for `\FLFsimpar` provided for backward-compatibility.

\staticaddexclusion { *IDN* } { *list* }

flowfram v1.14+

Appends *list* to the exclusion list for the static frame identified by its IDN. §3.1.1; 74

\staticframe

flowfram

Temporary box register used in as an intermediate when setting the contents of a static frame. §2.3; 42

\staticframeevenx{ $\langle IDN \rangle$ }

flowfram

Expands to the even-page x -coordinate of the static frame identified by its IDN. §3.1.3; 82

\staticframeeveny{ $\langle IDN \rangle$ }

flowfram

Expands to the even-page y -coordinate of the static frame identified by its IDN. §3.1.3; 83

\staticframeheight{ $\langle IDN \rangle$ }

flowfram

Expands to the height of the static frame identified by its IDN. §3.1.3; 80

\staticframewidth{ $\langle IDN \rangle$ }

flowfram

Expands to the width of the static frame identified by its IDN. §3.1.3; 80

\staticframex{ $\langle IDN \rangle$ }

flowfram

Expands to the x -coordinate of the static frame identified by its IDN. §3.1.3; 83

\staticframey { $\langle IDN \rangle$ }

flowfram

Expands to the y -coordinate of the static frame identified by its IDN. §3.1.3; 84

\staticsetexclusion { $\langle IDN \rangle$ } { $\langle list \rangle$ }

flowfram v1.14+

Sets the exclusion list for the static frame identified by its IDN. §3.1.1; 74

\staticsetpagelist { $\langle IDN \rangle$ } { $\langle page-list \rangle$ | $\langle keyword \rangle$ }

flowfram v1.14+

Sets the page list for the static frame identified by its IDN. §3.1.1; 72

\staticswitchoffnext { $\langle ID-list \rangle$ }

modifier: * flowfram v1.14+

Switch off the listed static frames from the next page onwards. §3.3; 98

\staticswitchoffnextodd { $\langle ID-list \rangle$ }

modifier: * flowfram v1.14+

Switch off the listed static frames from the next odd page onwards (after that they will be off for both even and odd pages). §3.3; 98

\staticswitchoffnextoddoneonly { $\langle ID-list \rangle$ }

modifier: *

flowfram v1.14+

Switch off the listed static frames for the next odd page only. §3.3; 98

\staticswitchoffnextonly{ *⟨ID-list⟩* } *modifier:* * flowfram v1.14+

Switch off the listed static frames for the next page only. §3.3; 98

\staticswitchonnext{ *⟨ID-list⟩* } *modifier:* * flowfram v1.14+

Switch on the listed static frames from the next page onwards. §3.3; 97

\staticswitchonnextodd{ *⟨ID-list⟩* } *modifier:* * flowfram v1.14+

Switch on the listed static frames from the next odd page onwards (after that they will show on both even and odd pages). §3.3; 98

\staticswitchonnextoddoneonly{ *⟨ID-list⟩* } *modifier:* *
flowfram v1.14+

Switch on the listed static frames for the next odd page only. §3.3; 98

\staticswitchonnextonly{ *⟨ID-list⟩* } *modifier:* * flowfram v1.14+

Switch on the listed static frames for the next page only. §3.3; 98

T

\thumbtabformat {*⟨text⟩*} {*⟨height⟩*}

flowfram

Used to format the thumbtab text. §6.1; 141

\thumbtabhyperlinkformat {*⟨anchor⟩*} {*⟨text⟩*} {*⟨height⟩*}

flowfram v2.0

If hyperref is loaded, this command will be redefined to create a hyperlink for the thumbtab frame content. §6.1; 141

\thumbtabindex [*⟨page-list⟩*]

flowfram

Used internally by flowfram's modified `\tableofcontents` to show the thumbtab index frames. However, if `adjust-toc=off` has been used to prevent this, the thumbtab index frames can be switched on with `\thumbtabindex`. §6.1; 140

\thumbtabindexformat {*⟨anchor⟩*} {*⟨text⟩*} {*⟨height⟩*}

flowfram

Used to format the content of the thumbtab index frames. §6.1; 141

\thumbtabregularformat {*⟨anchor⟩*} {*⟨text⟩*} {*⟨height⟩*} flowfram v2.0+

Used to format the content of the thumbtab (non-index) frames. §6.1; 141

\thumbtabwidth*initial:* 1 cm flowfram

The default width of thumbtabs. §6.1; 138

\twocolumn [*<page-list>*] [*<label>*]

(redefined by flowfram)

Creates two flow frames that fit in the typeblock separated by the distance given by `\columnsep`, with the height adjusted if the conditional `\iffvadjust` is true. §5.1; 112

\twocolumnbottom [*<page-list>*] {*<type>*} {*<bottom-height>*} [*<label>*]

flowfram

(preamble only)

As `\twocolumnbottominarea` where the area is given by the typeblock. §5.2; 124

\twocolumnbottominarea [*<page-list>*] {*<type>*} {*<bottom-height>*}{*<width>*} {*<height>*} {*<x>*} {*<y>*} [*<label>*]

flowfram

(preamble only)

Creates a frame of the given type (flow, static or dynamic) and height *<top-height>* and two side-by-side flow frames that all fit in the given area such that the first frame is below the other two frames, separated by `\vcolumnsep`. The height of the two side-by-side flow frames is adjusted if `\iffvadjust` is true. The horizontal gap between them is given by `\columnsep`. §5.2; 117

\twocolumnDbottom [*<page-list>*] { *<bottom-height>* } [*<label>*] flowfram
(preamble only)

As \twocolumnbottom with the *<type>* set to dynamic. §5.2; 124

\twocolumnDbottominarea [*<page-list>*] { *<bottom-height>* } { *<width>* }
{ *<height>* } { *<x>* } { *<y>* } [*<label>*] flowfram
(preamble only)

As \twocolumnbottominarea with the *<type>* set to dynamic. §5.2; 124

\twocolumnDtop [*<page-list>*] { *<top-height>* } [*<label>*] flowfram
(preamble only)

As \twocolumntop with the *<type>* set to dynamic. §5.2; 120

\twocolumnDtopinarea [*<page-list>*] { *<top-height>* } { *<width>* }
{ *<height>* } { *<x>* } { *<y>* } [*<label>*] flowfram
(preamble only)

As \twocolumntopinarea with the *<type>* set to dynamic. §5.2; 119

```
\twocolumninarea [ <page-list> ] { <width> } { <height> } { <x> } { <y> }
[ <labels> ] flowfram
(preamble only)
```

Creates two flow frames that span the given area separated by the distance given by `\columnsep`, with the height adjusted if the conditional `\ifffvadjust` is true. [§5.1](#); 114

```
\twocolumnSbottom [ <page-list> ] { <bottom-height> } [ <label> ] flowfram
(preamble only)
```

As `\twocolumnbottom` with the *<type>* set to `static`. [§5.2](#); 124

```
\twocolumnSbottominarea [ <page-list> ] { <bottom-height> } { <width> }
{ <height> } { <x> } { <y> } [ <label> ] flowfram
(preamble only)
```

As `\twocolumnbottominarea` with the *<type>* set to `static`. [§5.2](#); 123

```
\twocolumnStop [ <page-list> ] { <top-height> } [ <label> ] flowfram
(preamble only)
```

As `\twocolumntop` with the *<type>* set to `static`. [§5.2](#); 120

\twocolumnstopinarea [*<page-list>*] {*<top-height>*} {*<width>*}
 {*<height>*} {*<x>*} {*<y>*} [*<label>*] flowfram
 (preamble only)

As `\twocolumntopinarea` with the *<type>* set to `static`. §5.2; 119

\twocolumntop [*<page-list>*] {*<type>*} {*<top-height>*} [*<label>*] flowfram
 (preamble only)

As `\twocolumntopinarea` where the area is given by the `typeblock`. §5.2; 119

\twocolumntopinarea [*<page-list>*] {*<type>*} {*<top-height>*} {*<width>*}
 {*<height>*} {*<x>*} {*<y>*} [*<label>*] flowfram
 (preamble only)

Creates a frame of the given type (flow, static or dynamic) and height *<top-height>* and two side-by-side flow frames that all fit in the given area such that the first frame is above the other two frames, separated by `\vcolumnsep`. The height of the two side-by-side flow frames is adjusted if `\iffvadjust` is true. The horizontal gap between them is given by `\columnsep`. §5.2; 116

\typeblockheight flowfram v2.0+

A length (dimension) that stores the height of the typeblock (initialised to `\textheight`). §1; 2

\typeblockoffsety

flowfram v2.0+

A length (dimension) that stores the vertical offset of the typeblock (initialised to the sum of \topmargin, \headheight, \headsep and \voffset). §1; 2

\typeblockwidth

flowfram v2.0+

A length (dimension) that stores the width of the typeblock (initialised to \textwidth). §1; 2

V

\vcolumnsep

initial: \columnsep flowfram

The vertical distance between the top/bottom frame and the column flow frames when using commands like \Ncolumnstop. §7.2; 149

\vNtone [*page-list*] [*x-offset*] {*n*} {*WI*} {*CI*} {*LI*} ... {*Wn*}
{*Cn*} {*Ln*}

flowfram

As \vtwotone but creates *n* static frames. §5.4.1; 129

\vNtonebottom [*page-list*] [*x-offset*] {*n*} {*H*} {*W1*} {*CI*}
 {*L1*} ... {*Wn*} {*Cn*} {*Ln*} flowfram

As \vtwotonebottom but creates *n* static frames. §5.4.1; 130

\vNtonetop [*page-list*] [*x-offset*] {*n*} {*H*} {*W1*} {*CI*} {*L1*}
 ... {*Wn*} {*Cn*} {*Ln*} flowfram

As \vtwotonetop but creates *n* static frames. §5.4.1; 130

\vtwotone [*page-list*] [*x-offset*] {*W1*} {*CI*} {*L1*} {*W2*} {*C2*}
 {*L2*} flowfram

Defines two side-by-side static frames where the first frame has width *W1*, background colour *CI* and label *L1*, and the second frame has width *W2*, background colour *CI* and label *L2*. Both frames have the height set to `\paperheight` and are positioned so that their base is at the bottom of the page, with the first frame offset from the left side of the page by *x-offset*. Note that the colour specifications *CI* and *C2* should be enclosed in braces, for example `{[gray]{0.5}}` not `[gray]{0.5}`. §5.4.1; 129

\vtwotonebottom [*page-list*] [*x-offset*] {*H*} {*W1*} {*CI*}
 {*L1*} {*W2*} {*C2*} {*L2*} flowfram

As \vtwotone but instead of being the full height of the page, the height for both frames is set to *H*. §5.4.1; 129

```
\vtwotonetop [⟨page-list⟩] [⟨x-offset⟩] {⟨H⟩} {⟨W1⟩} {⟨C1⟩} {⟨L1⟩}
{⟨W2⟩} {⟨C2⟩} {⟨L2⟩} flowfram
```

As `\vtwotonebottom` but vertically offset so that the top of the frames is at the top of the page. §5.4.1; 129

B.2. Environment Summary

```
\begin{dynamiccontents} [⟨options⟩] {⟨IDN⟩} flowfram v1.09+
```

Sets the contents of the dynamic frame identified by its IDN. Note that verbatim text can't occur within the environment body. §2.4; 50, 53, 65, 67, 186, 194, 252

```
\begin{dynamiccontents*} [⟨options⟩] {⟨IDL⟩} flowfram
```

Sets the contents of the dynamic frame identified by its IDL. Note that verbatim text can't occur within the environment body. §2.4; 53, 65, 67, 186, 252

```
\begin{staticcontents} [⟨options⟩] {⟨IDN⟩} flowfram
```

Sets the contents of the static frame identified by its IDN. §2.3; 41, 42, 43, 47, 48, 50, 194, 252

```
\begin{staticcontents*} [\langle options \rangle] { \langle IDL \rangle }
```

flowfram

Sets the contents of the static frame identified by its IDL. §2.3; 42, 43, 253

```
\begin{staticfigure}
```

flowfram

Simulate a figure in a static or dynamic frame. §1.3; 28, 185, 253

```
\begin{statictable}
```


flowfram

Simulate a table in a static or dynamic frame. §1.3; 28, 185, 253



```
\usepackage[<options>]{flowfram}
```

C. Package Option Summary

Package for constructing custom document columns and fixed frames. §1.2; 9, 255

adjust-pre-chapter=*<boolean>* *default: true; initial: true*  flowfram v2.0+
(package option only)

If true and \chapter is defined, this setting will define \ffprechapterhook and \chapterfirstpagestyle. §1.2.4; 25, 32, 255

adjust-toc=*<setting>*  flowfram v2.0+
Specifies whether or not the table of contents should be adjusted to support thumbtab indexes and mini-tocs. §1.2.1; 11, 255

adjust-toc=header


Adjust the table of contents, including the header. 11, 255

adjust-toc=noheader

Adjust the table of contents, but not the header. 11, 255

adjust-toc=off

Don't adjust the table of contents, which means there won't be any support for thumbtab indexes or mini-tocs. 11, 12, 140, 245, 255

backmatter-sections=*<setting>* *initial: no-number*  flowfram v2.0+
Classes that support \backmatter tend to suppress the chapter number but not section numbers. As this can cause interference, this option may be used to suppress section numbers as well. §1.2.1; 11, 255


backmatter-sections=no-change

Don't alter secnumdepth in the back matter. 12, 255

`backmatter-sections=no-number`


Suppress section numbers in the back matter (`\backmatter` will set `secnum-depth` to -1). 12, 256

`color=<boolean>`

default: true; *initial:* true  flowfram v1.0
(preamble only)

If true, enable colour support. §1.2.4; 27, 256, 259

`column-changes=<setting>`

initial: ignore  flowfram v2.0+

Indicates what to do if `\onecolumn` or `\twocolumn` are encountered in the document environment. §1.2.3; 22, 181, 256

`column-changes=clearpage`

Clear the page but otherwise ignore any instance of `\onecolumn` or `\twocolumn` found in the document environment. 23, 256

`column-changes=ignore`

Ignore any instance of `\onecolumn` or `\twocolumn` found in the document environment. 23, 256

`column-changes=switch`


Switch to the designated frames. 23, 239, 240, 256

`draft`

 flowfram v1.0+

Switches on draft mode. §1.2.4; 2, 5, 25, 28–31, 181, 256

`dynamic-empty-page-style={<value>}`

initial: hide  flowfram v2.0+

Controls how the `fempty` page style behaves with dynamic header and footer frames. §1.2.2; 20, 21, 62, 63, 256

`dynamic-empty-page-style=empty`

The header and footer frames have their contents set to empty but will still be shown on the page. 20, 63, 256

`dynamic-empty-page-style=headings`

Behaves like `ffheadings`. 20, 257

`dynamic-empty-page-style=hide`

The `hide` attribute will be switched on with `\pagestyle` and the `hidethis` attribute will be switched on with `\thispagestyle`. 20, 21, 257

`dynamic-empty-page-style=ignore`

The style will do nothing, retaining the current page style. 21, 257

`dynamic-empty-page-style=myheadings`

Behaves like `ffmyheadings`. 21, 257

`dynamic-empty-page-style=plain`

Behaves like `ffplain`. 20, 257

`dynamic-empty-page-style=show`

The `hide` or `hidethis` attribute won't be switched on by the `ffempty` style. 20, 21, 257

`dynamic-header-case=<setting>` *initial: no-change*  flowfram v2.0+

Indicates whether or not `\chaptermark` (if chapters are defined) or `\sectionmark` (otherwise) with the `ffheadings` and `ffmyheadings` styles should change the case of the header text. §1.2.2; 18, 61, 62, 257

`dynamic-header-case=no-change`

Don't change the case of the header. 18, 257

`dynamic-header-case=uc`

Change the header to uppercase. 18, 257

`dynamic-page-style-header-font={ <code> }` *initial: \emph* 

flowfram v2.0+

Use the given `<code>` to set the font used by `\chaptermark` (if chapters are available) or `\sectionmark` (otherwise) with `ffheadings`. The `<code>` may be declarations or the final command in `<code>` may be a text-block command. §1.2.2; 19, 61, 62, 257, 258

dynamic-page-style-subheader-font= $\{\langle code \rangle\}$  flowfram v2.0+

Use the given $\langle code \rangle$ to set the font used by `\sectionmark` (if chapters are available) or `\subsectionmark` (otherwise) with `ffheadings`. Initialised to match `dynamic-page-style-header-font`. §1.2.2; 19, 62, 258

dynamic-page-style= $\langle setting \rangle$ *initial:* `adjust`  flowfram v2.0+
(preamble only)


Indicates whether or not to adjust the standard page styles if the header and footer are converted into dynamic frames. §1.2.2; 17, 226, 258

`dynamic-page-style=adjust`

If used, `\makedfheaderfooter` will set (`\let`) the `empty`, `plain`, `headings` and `myheadings` page styles to `ffempty`, `ffplain`, `ffheadings` and `ffmyheadings`. 18, 20, 65, 258

`dynamic-page-style=noadjust`

Don't adjust the `empty`, `plain`, `headings` and `myheadings` page styles. 18, 258

dynamic-subheader-case= $\langle setting \rangle$ *initial:* `no-change`  flowfram v2.0+

Indicates whether or not `\sectionmark` (if chapters are defined) or `\subsectionmark` (otherwise) with the `ffheadings` and `ffmyheadings` styles should change the case of the sub-header text. §1.2.2; 18, 62, 258

`dynamic-subheader-case=no-change`

Don't change the case of the sub-header. 19, 258

`dynamic-subheader-case=uc`

Change the sub-header to uppercase. 19, 258

final

 flowfram v1.0

Switches off draft mode. §1.2.4; 25, 258

LR

 flowfram v1.12+

(preamble only)

The column commands, such as `\twocolumn`, will create flow frames from left to right. §1.2.3; 22, 112, 127, 221, 258

`matter-thumbtabs`=*⟨setting⟩*  flowfram v2.0+

Indicates whether or not unstarred sectional units outside of the main matter should have thumbtabs. §1.2.1; 10, 13, 139, 259

`matter-thumbtabs`=**`all`**

Support thumbtabs for unstarred units everywhere. 14, 259

`matter-thumbtabs`=**`main-only`**

Only have thumbtabs for unstarred units in the main matter. 13, 259


`matter-thumbtabs`=**`not-back`**

Only have thumbtabs for unstarred units in the main matter and front matter but not in the back matter. 14, 259

`matter-thumbtabs`=**`not-front`**

Only have thumbtabs for unstarred units in the main matter and back matter but not in the front matter. 14, 259

`nocolor`

 flowfram v1.0
(preamble only)


Equivalent to `color=false`. §1.2.4; 27, 259

`norotate`

 flowfram v1.0

Prevents frame rotation and sets `thumbtab-text=stack`. §1.2.4; 26, 259

`pages`=*⟨setting⟩*

initial: relative  flowfram v1.14+
(preamble only)

Indicates which value page lists refer to. §1.2.4; 24, 36, 73, 189, 259

`pages=absolute`

All page lists refer to the absolute page counter. 2, 4, 25, 73, 94, 260

`pages=relative`


All page lists refer to the page counter. 4, 25, 73, 260

`prohibit-frame-rotation`=*<boolean>* *default: true; initial: false* 

flowfram v2.0+

If true, disable frame rotation. §1.2.4; 26, 260


RL

 flowfram v1.12+
(preamble only)

The column commands, such as `\twocolumn`, will create flow frames from right to left. §1.2.3; 22, 112, 127, 221, 260

`rotate`=*<boolean>* *default: true; initial: false*  flowfram v1.0

If true, enables frame rotation and sets `thumbtab-text=rotate-right`. §1.2.4; 26, 260

`sections-extra-option`=*<setting>*  flowfram v2.0+

Indicates whether or not the second optional argument of sectioning commands should be passed to the original or just be used for the thumbtab title. §1.2.1; 16, 192, 235, 237, 260

`sections-extra-option=as-original`

Indicates that the underlying command has a second optional argument and any second optional argument should simply be passed and not used as the thumbtab title. 17, 260


`sections-extra-option=original-and-thumbtab`

Indicates that the underlying command has a second optional argument and any second optional argument should be both passed to the underlying command and used as the thumbtab title (if enabled). 17, 260

`sections-extra-option=thumbtab-only`

Indicates that the second optional argument (if present) should only be used as the thumbtab title (if enabled) and not passed to the underlying command. 17, 261

`thumbtab-links=<setting>`

 flowfram v2.0+

Indicates which thumbtabs should have `\hyperlinks` (if supported). §1.2.1; 14, 141, 261

`thumbtab-links=all`

Have `\hyperlinks` in all the thumbtabs. 14, 261

`thumbtab-links=none`

Don't have `\hyperlinks` in any of the thumbtabs. 15, 261

`thumbtab-links=toc-only`

Only have `\hyperlinks` in the thumbtab indexes. 14, 261

`thumbtab-text=<setting>`

initial: rotate  flowfram v2.0+

Indicates how the text should be shown in the thumbtabs. §1.2.1; 15, 141, 261

`thumbtab-text=normal`

No rotation or stacking. 15, 261

`thumbtab-text=rotate-left`

Rotate the text to the left. 15, 261

`thumbtab-text=rotate-right`


Rotate the text to the right. 15, 26, 260, 261

`thumbtab-text=rotate`

Turn the text sideways. 15, 261

`thumbtab-text=stack`

Stack the letters vertically. 15, 26, 259, 261

thumbtabs= $\langle setting \rangle$
 flowfram v1.14+
(preamble only)

Indicates whether or not the number or title should be shown in the thumbtabs. §1.2.1; 16, 26, 27, 262

thumbtabs=both

Show both the number (if applicable) and the title. 16, 262

thumbtabs=none


Don't show either the number or title. 16, 262

thumbtabs=number

Only show the number (if applicable). 16, 262

thumbtabs=title

Only show the title. 16, 262

toc-thumbtabs= $\langle setting \rangle$
default: true; initial: false  flowfram v2.0+

Sets whether or not to show the thumbtab index frames in the table of contents (if thumbtabs have been created). §1.2.1; 12, 262

toc-thumbtabs=aligned

Separate the table of contents into blocks that are the same height as the corresponding thumbtab (for single-paged table of contents only). 12, 262

toc-thumbtabs=false

Don't show the thumbtab indexes in the table of contents. 13, 262

toc-thumbtabs=true

Show the thumbtab indexes on every page of the table of contents. 13, 262

toc-thumbtabs=unaligned

Don't align sub-blocks of the table of contents with the thumbtabs and only show the thumbtab indexes on the first page of the table of contents. 12, 262

ttbnonum

≡ flowfram v1.0
(preamble only)

Don't include the number in the thumbtabs (if enabled). §1.2.4; 27, 263, *see* thumbtabs

ttbnotitle

≡ flowfram v1.0
(preamble only)

Don't include the title in the thumbtabs (if enabled). §1.2.4; 26, 263, *see* thumbtabs

ttbnum


≡ flowfram v1.0
(preamble only)

Include the number in the thumbtabs (if enabled). §1.2.4; 27, 263, *see* thumbtabs


ttbtitle

≡ flowfram v1.0
(preamble only)

Include the title in the thumbtabs (if enabled). §1.2.4; 26, 263, *see* thumbtabs


unstarred-thumbtabs=*<boolean>* *default: true; initial: false* 
flowfram v2.0+


Indicates whether or not unstarred units should have thumbtabs. §1.2.1; 10, 13, 263

verbose=*<boolean>* *default: true; initial: false*  flowfram v1.14+
Switches on/off verbose mode. §1.2.4; 25, 263

```
\usepackage[<options>]{flowframtkutils}
```

Supplementary package for use with flowframtk. §8.4; 78, 153, 155, 156–158, 160, 163, 164, 187, 211–215, 223, 224, 263, 264

outline=*<boolean>* *default: true; initial: false*  flowframtkutils
If true, provide support for outline text according to the T_EX engine. §8.4.1; 156, 158, 224, 263

`path`=*<boolean>* *default: true; initial: false*  flowframtkutils
provide support for text along a path. §8.4.1; 156, 264

Symbols

\@evenfoot 62–64
 \@evenhead 62–64
 \@makechapterhead 58
 \@oddfoot 62–64
 \@oddhead 62–64

A

absolute page counter §7.3; 24, 25, 31, 36,
 73, 89, 150, 260
 \adjustcolsep §5; 111, 191
 \afterminitocskip §6.2; 146, 191
 \appenddfminitoc .. §6.2; 75, 144,
 145, 191, *see also*
 \enableminitoc
 \appenddynamiccontents §2.4;
 53, 55, 67, 191
 \appendix 140


B

back matter 13, 14, 255, 256, 259
 \backmatter 11, 12, 255, 256
 \baselineskip 112, 115, 221
 beamer class 161, 164, 165
 \beforeminitocskip §6.2;
 145, 192
 book class 57–59, 202, 203
 bounding box . 5, 28–30, 85, 91, 147, 148,
 180, 187, 205, 223, 238

C

\caption 28
 \centering 160
 \chapter 13, 25, 32, 33, 54, 55, 61–64,
 75, 92, 139, 140, 145, 192, 195,
 206, 255
 \chapterfirstpagestyle §1.6;
 25, 33, 192, 255
 \ChapterInDynamic §2.4.1; 54, 55,
 75, 145, 192, 195
 \chaptermark 18, 19, 64, 257
 \cleardoublepage .. 4, 33, 39, 55,
 95, 192
 \clearpage .. 23, 32, 33, 39, 55, 183,
 193, 208
 \cleartoevenpage §2.1.1; 39, 192
 \color 86–88
 color §8.4.2.2; 176
 color package 27
 \columnsep §7.2; 111, 112, 114, 149,
 191, 226–228, 230, 246, 248, 249
 \columnseprule 132
 \computebottomedge §4.1;
 102, 193
 \computeflowframearea
 193, 201
 \computeleftedgeeven ... §4.1;
 101, 193
 \computeleftedgeodd §4.1;
 101, 193

Index

- `\computerightedgeeven` .. §4.1; 102, 194
- `\computerightedgeodd` ... §4.1; 102, 194
- `\computetopedge` .. §4.1; 101, 194
- `\continueonframe` §2.3.1; 43, 45–47, 49, 65, 66, 67, 107, 194, 204, 205
- D**
- `\defaultthumbtabtype` ... §6.1; 138, 195
- `\dfchaphead`  54, 195
- `\dfchapterclearpage` ... §2.4.1; 55, 195
- `\dfEvenFooterStyle` . §2.4.2; 61, 64, 195
- `\dfEvenHeaderStyle` §2.4.2; 61, 195
- `\dfOddFooterStyle` ... §2.4.2; 61, 64, 196
- `\dfOddHeaderStyle` ... §2.4.2; 61, 64, 196
- `\dfswapoddeven` ... §3.1.3; 85, 196
- `\disablethumbtabs` §6.1; 10, 140, 196
- `displayedframe` counter §7.3; 151, 225, *see also* `thisframe`
- `document` environment 1, 4, 23, 32, 35, 89, 94, 187, 189, 208, 239, 240, 256
- `\doublebox` 79, 85
- `dx` §8.4.2.2; 166, 175
- `dy` §8.4.2.2; 166, 175
- `dynamic frame` 4, 19, 50, 51, 69, 75, 76, 78, 89, 106, 187, 188, 227, 230, 232, 235–237, 246, 249
- `dynamic frame (special)` . *see* special labels
- `\dynamicaddexclusion` .. §3.1.1; 74, 196
- `dynamiccontents` environment §2.4; 50, 53, 65, 67, 186, 194, 252
- `dynamiccontents*` environment §2.4; 53, 65, 67, 186, 252
- `\dynamicframeevenx` §3.1.3; 82, 197
- `\dynamicframeeveny` §3.1.3; 83, 197
- `\dynamicframeheight` ... §3.1.3; 81, 197
- `\dynamicframewidth` §3.1.3; 80, 197
- `\dynamicframex` ... §3.1.3; 83, 197
- `\dynamicframey` ... §3.1.3; 84, 197
- `\dynamicsetexclusion` .. §3.1.1; 74, 198
- `\dynamicsetpagelist` ... §3.1.1; 72, 198
- `\dynamicswitchoffnext` .. §3.3; 96, 198
- `\dynamicswitchoffnextodd` §3.3; 97, 198
- `\dynamicswitchoffnextodd-`

- only §3.3; 97, 198
- \dynamicsswitchoffnextonly
§3.3; 97, 199
- \dynamicsswitchonnext ... §3.3;
96, 199
- \dynamicsswitchonnextodd
§3.3; 97, 199
- \dynamicsswitchonnextodd-
only §3.3; 97, 199
- \dynamicsswitchonnextonly
§3.3; 97, 199
- enable §8.4.2.1; 174
- E**
- \enableminitoc §6.2; 144, 191, 200
- \enablethumtbs .. §6.1; 10, 139,
140, 200, 226
- end §8.4.2.2; 176
- \evensidemargin 4, 101
- F**
- fancybox package 6, 85
- \fbox 79, 148, 185, 188
- \fboxrule 209
- \fboxsep 148, 209
- \fcolorbox 86
- \FFabove §4.3; 105, 108, 109, 200, 222
- \FFaboveleft §4.3; 104, 200
- \FFaboveright §4.3; 104, 200
- \ffareaheight 103, 193, 201,
217–219
- \ffareawidth 103, 193, 201,
217–219
- \ffareax 103, 193, 201, 217–219
- \ffareay 103, 193, 201, 217–219
- \FFbelow §4.3; 105, 201
- \FFbelowleft §4.3; 105, 201
- \FFbelowright §4.3; 105, 202
- \ffchapterdefaultfont §2.4.1;
58, 59, 202
- \ffchapterheadstyle ... §2.4.1;
58, 202
- \ffchapternamenum §2.4.1;
59, 202
- \ffchapternamenumfont §2.4.1;
59, 202
- \ffchapterpostheadskip
§2.4.1; 58, 203
- \ffchapterpostnamenum §2.4.1;
59, 203
- \ffchapterpreheadskip §2.4.1;
58, 203
- \ffchaptertitlefont ... §2.4.1;
59, 203
- \ffcolumseprule ... §5.4.4; 132,
133, 203
- \ffcontinuedtextfont .. §2.3.1;
46, 204, *see also*
 \continueonframe
- \ffcontinuedtextlayout
§2.3.1; 46, 47, 204
- \ffdefaultcontinuetext

- [§2.3.1](#); 46, 67, 204
- `\ffdefaultdynamiccontinue-`
 `text` [§2.4.3](#); 46, 67, 204
- `\ffdefaultpostcontinued`
 [§2.3.1](#); 47, 48, 67, 204, *see also*
 `\continueonframe`
- `\ffdefaultstaticcontinue-`
 `text` [§2.3.1](#); 45, 67, 194,
 204, 205
- `\ffdynamicpostcontinued`
 [§2.4.3](#); 67, 204, 205, *see also*
 `\continueonframe`
- `\ffhrule` [§5.4.4](#); 134, 135, 205
- `\fflabelfont` [§7.1](#); 147, 205
- `\fflabelsep` [§7.2](#); 148, 205
- `\FFleft` [§4.3](#); 105, 206
- `\FFoverlap` [§4.3](#); 105, 206
- `\ffprechapterhook` . [§1.6](#); 25, 32,
 206, 255
- `\FFright` [§4.3](#); 105, 206
- `\ffruleddeclarations` ... [§5.4.4](#);
 133, 134, 206
- `\ffstaticpostcontinued`
 [§2.3.1](#); 47, 48, 67, 204, 206, *see*
 also `\continueonframe`
- `\ffswapoddeven` ... [§3.1.3](#); 84, 207
- `\fftolerance` [§2.1.1](#); 39, 207
- `\ffvadjustfalse` .. [§5.1](#); 113, 207
- `\ffvadjusttrue` [§5.1](#); 114, 115, 207
- `\ffvrule` [§5.4.4](#); 133, 135, 207
- figure environment 27, 28
- figure* environment 27, 32
- file formats
 - aux 89, 107, 186
 - cls 154, 187
 - sty 154, 187
 - tex 153
 - toc 11, 186
 - tth [§6.1](#); 10, 137, 186, 196, 200, 226
- `\finishthispage` [§2.1.1](#); 31,
 39, 208
- fixed [§8.4.2.1](#); 174
- `\FLFsimpar` 92, 208, 241
- flow frame 35, 69, 107, 187, 188, 227, 230,
 232, 235, 236, 246, 249
- `\flowaddexclusion` [§3.1.1](#);
 74, 208
- flowfram package [§1.2](#); 9, 255
 - `adjust-pre-chapter` . [§1.2.4](#);
 25, 32, 255
 - `adjust-toc` [§1.2.1](#); 11, 255
 - header 11, 255
 - noheader 11, 255
 - off 11, 12, 140, 245, 255
- `backmatter-sections`
 [§1.2.1](#); 11, 255
 - no-change 12, 255
 - no-number 12, 256
- color [§1.2.4](#); 27, 256, 259
- `column-changes` ... [§1.2.3](#); 22,
 181, 256
- `clearpage` 23, 256

- ignore 23, 256
- switch 23, 239, 240, 256
- draft §1.2.4; 2, 5, 25, 28–31, 181, 256
- dynamic-empty-page
 - style §1.2.2; 20, 21, 62, 63, 256
- empty 20, 63, 256
- headings 20, 257
- hide 20, 21, 257
- ignore 21, 257
- myheadings 21, 257
- plain 20, 257
- show 20, 21, 257
- dynamic-header-case
 - §1.2.2; 18, 61, 62, 257
- no-change 18, 257
- uc 18, 257
- dynamic-page-style
 - header-font §1.2.2; 19, 61, 62, 257, 258
- dynamic-page-style
 - subheader-font .. §1.2.2; 19, 62, 258
- dynamic-page-style . §1.2.2; 17, 226, 258
 - adjust 18, 20, 65, 258
 - noadjust 18, 258
- dynamic-subheader-case
 - §1.2.2; 18, 62, 258
- no-change 19, 258
- uc 19, 258
- final §1.2.4; 25, 258
- LR §1.2.3; 22, 112, 127, 221, 258
- matter-thumbtabs §1.2.1; 10, 13, 139, 259
 - all 14, 259
 - main-only 13, 259
 - not-back 14, 259
 - not-front 14, 259
- nocolor §1.2.4; 27, 259
- norotate §1.2.4; 26, 259
- pages . §1.2.4; 24, 36, 73, 189, 259
 - absolute .. 2, 4, 25, 73, 94, 260
 - relative 4, 25, 73, 260
- prohibit-frame-rotation
 - §1.2.4; 26, 260
- RL §1.2.3; 22, 112, 127, 221, 260
- rotate §1.2.4; 26, 260
- sections-extra-option
 - §1.2.1; 16, 192, 235, 237, 260
- as-original 17, 260
- original-and-thumbtab
 - 17, 260
- thumbtab-only 17, 261
- thumbtab-links ... §1.2.1; 14, 141, 261
 - all 14, 261
 - none 15, 261
 - toc-only 14, 261
- thumbtab-text §1.2.1; 15,

- 141, 261
- normal 15, 261
- rotate-left 15, 261
- rotate-right 15, 26, 260, 261
- rotate 15, 261
- stack 15, 26, 259, 261
- thumbtabs* §1.2.1; 16, 26, 27, 262
 - both 16, 262
 - none 16, 262
 - number 16, 262
 - title 16, 262
- toc-thumbtabs* §1.2.1; 12, 262
 - aligned 12, 262
 - false 13, 262
 - true 13, 262
 - unaligned 12, 262
- ttbnonum* §1.2.4; 27, 263, *see* *thumbtabs*
- ttbnotitle* §1.2.4; 26, 263, *see* *thumbtabs*
- ttbnum* §1.2.4; 27, 263, *see* *thumbtabs*
- ttbtitle* §1.2.4; 26, 263, *see* *thumbtabs*
- unstarred-thumbtabs* §1.2.1; 10, 13, 263
- verbose* §1.2.4; 25, 263
- `\flowfram@doc@html`opts §3.1.5; 89, 208
- `\flowfram@preamble@html`opts §3.1.5; 89, 208
- `\flowframchapterheader` §2.4.2; 61, 64, 209
- `\flowframeevenx` .. §3.1.3; 82, 209
- `\flowframeeveny` .. §3.1.3; 82, 209
- `\flowframeheight` §3.1.3; 80, 209
- `\flowframerule` §7.2; 85, 148, 209
- `\flowframesep` §7.2; 148, 209
- `\flowframeshowlayout` §1.4; 30, 31, 210
- `\flowframewidth` .. §3.1.3; 80, 210
- `\flowframex` §3.1.3; 83, 210
- `\flowframey` §3.1.3; 84, 210
- `\flowframheaderchapprefix` §2.4.2; 62, 210
- `\flowframheadersep` §2.4.2; 62, 210
- `\FlowFramRestoreOR` . §1.5; 1, 28, 31, 211
- `\flowframsectionheader` §2.4.2; 62, 64, 211
- `\flowframsetup` §1.2; 10, 211
- `\flowframsubsectionheader` 64, 211
- `FlowframTk` 1, 6, 38, 60, 78, 79, 86, 87, 90, 91, 113, 137, 138, 143, 153–161, 166, 167, 181, 187, 188
- `flowframtk` §8; 153, 263
- `\FlowframTkBeginScopeIfGroup` §8.4.2; 163, 211
- `\flowframtkencapobject` §8.4.2; 161, 162, 164, 212,

- 213, 214
- \flowframtkendobject .. §8.4.2;
161, 162, 163, 212, 214
- \FlowframTkEndScopeIf-
Group §8.4.2; 163, 212
- \flowframtkimageinfo .. §8.4.2;
159, 212
 - creationdate §8.4.2; 159
 - title §8.4.2; 159
- \flowframtkimgtitlechar
§8.4.2; 160, 213
- \flowframtkNoRagged ... §8.4.2;
160, 213
- \FlowframTkScopeIfGroup
§8.4.2; 164, 213
- \flowframtkSetCreation-
Date §8.4.2; 159, 213
- \flowframtkSetTitle ... §8.4.2;
159, 213
- \flowframtkstartobject
§8.4.2; 161, 162, 163, 211,
212, 214
- flowframtkutils package §8.4; 78, 153, 155,
156–158, 160, 163, 164, 187,
211–215, 223, 224, 263, 264
 - outline §8.4.1; 156, 158, 224, 263
 - textpath §8.4.1; 156, 264
- \FlowFramTkUtilsOverlayEn-
capSetup ... §8.4.2; 165, 214
 - annotate-arrow . §8.4.2; 166, 170,
171, 174, 175
 - annotate-position . §8.4.2; 169
 - auto 169
 - east 169
 - north 169
 - northeast 169
 - northwest 170
 - south 170
 - southeast 170
 - southwest 170
 - west 170
 - annotate-text ... §8.4.2; 166, 170
 - description-or-tag .. 171
 - description 171
 - hide 171
 - tag-map 171
 - tag 171
 - annotate §8.4.2; 166, 167, 168
 - false 169
 - from 168
 - match 168
 - single 168
 - true 169
 - auto-overlay §8.4.2; 166,
172, 173
 - fallback-overlay §8.4.2; 166,
172, 173, 174
 - object-overlay .. §8.4.2; 166,
172, 173, 174
 - tag-overlay .. §8.4.2; 166, 167,
172, 174
 - tag-text §8.4.2; 171

- `uncover` §8.4.2; 167, 168
 - `false` 168
 - `from` 168
 - `single` 167
 - `\FlowFramTkUtilsSetOverlayEncap` §8.4.2; 164, 165, 214
 - `\flowframtkutils_uncover_encap:nnnnnnnn` ... §8.4.2; 164, 165, 214, 215
 - `\flowframtkutils_uncover_from:nn` ... §8.4.2; 165, 215
 - `\flowframtkutils_uncover:nn` §8.4.2; 165, 215
 - `\FlowFramUnrestoreOR` . §1.5; 1, 28, 32, 215
 - `\flowsetexclusion` §3.1.1; 74, 215
 - `\flowsetpagelist` §3.1.1; 72, 215
 - `\flowswitchoffnext` §3.3; 95, 216
 - `\flowswitchoffnextodd` .. §3.3; 96, 216
 - `\flowswitchoffnextoddoneonly` §3.3; 96, 216
 - `\flowswitchoffnextonly` §3.3; 96, 216
 - `\flowswitchonnext` §3.3; 95, 216
 - `\flowswitchonnextodd` ... §3.3; 95, 216
 - `\flowswitchonnextoddoneonly` §3.3; 96, 217
 - `\flowswitchonnextonly` .. §3.3; 96, 217
 - footer frame .. 20, 21, 60, 60, 61–64, 188, 195, 196
 - footer (page) .. 60, *see also* footer frame & page styles
 - frame 69, 188
 - dynamic *see* dynamic frame
 - flow *see* flow frame
 - static *see* static frame
 - frame making command 85, 148, 188
 - `\framebreak` ... §2.1.1; 38, 182, 217
 - front matter 13, 14, 24, 139, 259
- ## G
- `\geometry` 1
 - geometry package 1, 2, 31
 - `\getdynamicbounds` §4.2; 103, 217
 - `\getdynamicid` §2.4; 52, 218
 - `\getdynamiclabel` .. §2.4; 51, 218
 - `\getflowbounds` §4.2; 103, 218
 - `\getflowid` §2.1; 37, 218
 - `\getflowlabel` §2.1; 36, 218
 - `\getstaticbounds` . §4.2; 103, 219
 - `\getstaticid` §2.2; 41, 219
 - `\getstaticlabel` ... §2.2; 41, 219
 - graphicx package 157
- ## H
- header frame .. 20, 21, 60, 60, 61–64, 188,

- 195, 196
 header (page) . 60, *see also* header frame & page styles
`\headheight` 2, 250
`\headsep` 2, 250
`hide` §8.4.2.2; 175
`\hNtone` §5.4.2; 130, 219
`\hNtoneleft` §5.4.2; 131, 220
`\hNtoneright` §5.4.2; 131, 220
 hooks
 `flowfram/chaphead/after` ... §2.4.1; 55
 `flowfram/chaphead/before` .. §2.4.1; 55
 `flowfram/chaphead/box/after` §2.4.1; 56
 `flowfram/chaphead/box/before` . §2.4.1; 55, 58
 `flowfram/staticbox/after` §2.3; 43
 `flowfram/staticbox/before` §2.3; 42
`\hsize` 38, 182
`\htwotone` §5.4.2; 130, 131, 219, 220
`\htwotoneleft` ... §5.4.2; 130, 131, 220, 221
`\htwotoneright` §5.4.2; 131, 220, 221
`\hyperlink` 14, 15, 141, 261
 hyperref package 14, 141, 159, 245
`\hypersetup` 159
- ## I
- IDL (identification label) 1, 23, 24, 29, 35–37, 40–43, 49, 51–54, 65, 70, 71, 92, 93, 95, 103, 104, 106, 107, 131, 132, 144, 184, 185, 188, 191, 193, 194, 204, 205, 217–219, 223, 224, 230, 231, 236, 238, 239, 252, 253
 IDL (special) *see* special labels
 IDN (identification number) 1, 4–6, 22–24, 29, 35–37, 40–43, 45, 47, 51–54, 65, 67, 70–72, 77, 80–84, 89, 95, 103, 104, 106, 107, 112, 132, 142, 144, 150, 183, 184, 188, 191, 193, 194, 196–198, 204–210, 215, 217–219, 223–225, 230, 231, 236, 238, 239, 241–243, 252
`\iffvadjust` .. §5.1; 114, 149, 207, 221, 227, 228, 230–233, 235, 246, 248, 249
`\iflefttorightcolumns` .. §5.3; 127, 221, 225
`\IfSavedRelativeLocation-Above` §4.3; 109, 221
`\IfSavedRelativeLocation-Below` §4.3; 109, 222
`\IfSavedRelativeLocation-Eq` §4.3; 108, 109, 222
`\IfSavedRelativeLocation-Left` §4.3; 109, 222
`\IfSavedRelativeLocation-Right` §4.3; 109, 222
`\ifshowframebbox` §1.4; 30, 223, 240
`\ifshowmargins` §1.4; 29, 223, 241

- `\ifshowtypeblock` §1.4; 29, 223, 241
`\includegraphics` 157
`\includeteximage` §8.4.2; 157, 223
`increment` §8.4.2.1; 174
`\input` 91, 154, 157
`\inserthrule` §5.4.4; 133, 134, 135, 203, 205, 206, 223
`\insertvrule` §5.4.4; 132, 134, 135, 203, 206, 207, 224
`\item` 186
- J**
- `\jdrimagebox` §8.4.2; 158, 224
`\jdroutline` .. §8.4.2; 156, 158, 224
- K**
- `kpsewhich` 157
- L**
- `\label` 28, 50, 150, 181, 225
`\labelflow` §7.3; 151, 225
`\labelflowidn` . §7.3; 150, 151, 225
`\leftmark` 64
`\lefttorightcolumnfalse` §5.3; 127, 225
`\lefttorightcolumnstrue` §5.3; 127, 225
`\linewidth` 76, 92, 93, 184
- `lrbox environment` 42
`luatex85 package` 156
- M**
- `main matter` 13, 14, 24, 259
`\mainmatter` 4, 95, 140
`\makebackgroundframe` .. §5.4.3; 131, 225
`\makedfheaderfooter` §2.4.2; 17, 18, 20, 60, 65, 76, 188, 226, 258
`\makethumbtabs` .. §6.1; 10, 12, 76, 137, 138, 139, 142, 195, 196, 200, 226
`\marginpar` 111, 113
`\marginparwidth` 111, 191
`maxdynamic counter` §7.3; 150
`maxflow counter` §7.3; 150
`maxstatic counter` §7.3; 149
`maxthumbtabs counter` §7.3; 150
`memoir class` 16, 17, 57
`mini-toc` ... §6.2; 10, 11, 57, 75, 144, 145, 146, 191, 192, 200, 226, 255
`\minitocstyle` §6.2; 145, 226
- N**
- `\Ncolumn` §5.1; 2, 71, 114, 127, 149, 226
`\Ncolumnbottom` §5.2; 125, 227, 229
`\Ncolumnbottominarea` ... §5.2; 117, 125, 227, 228, 229

`\NcolumnDbottom` .. §5.2; 126, 227
`\NcolumnDbottominarea` .. §5.2; 125, 228
`\NcolumnDtop` §5.2; 121, 228
`\NcolumnDtopinarea` §5.2; 121, 228
`\Ncolumninarea` ... §5.1; 115, 228
`\NcolumnSbottom` .. §5.2; 126, 229
`\NcolumnSbottominarea` .. §5.2; 125, 229
`\NcolumnStop` §5.2; 121, 229
`\NcolumnStopinarea` §5.2; 120, 229
`\Ncolumnstop` ... §5.2; 121, 149, 228, 229, 250
`\Ncolumnstopinarea` ... §5.2; 116, 121, 228, 229, 230
`\newdynamicframe` ... §2.4; 51, 60, 154, 230
`\newflowframe` §2.1; 35, 40, 51, 111, 127, 154, 230
`\newframe` §5.2; 126, 231
`\newpage` 38, 208
`\newstaticframe` §2.2; 40, 154, 231
`\onecolumnbottom` §5.2; 122, 232, 233
`\onecolumnbottominarea` §5.2; 116, 122, 232, 234
`\onecolumnDbottom` §5.2; 123, 232
`\onecolumnDbottominarea` §5.2; 122, 232
`\onecolumnDtop` ... §5.2; 118, 233
`\onecolumnDtopinarea` ... §5.2; 118, 233
`\onecolumninarea` ... §5.1; 21, 23, 114, 221, 233
`\onecolumnSbottom` §5.2; 123, 233
`\onecolumnSbottominarea` §5.2; 122, 234
`\onecolumnStop` §5.2; 118, 234
`\onecolumnStopinarea` ... §5.2; 117, 234
`\onecolumnstop` . §5.2; 118, 233, 234
`\onecolumnstopinarea` §5.2; 116, 118, 233, 234, 235
output routine .. b, 1, 9, 22, 28, 31, 32, 69, 73, 76, 88, 89, 127, 151
`\Ovalbox` 79, 85
`\ovalbox` 79, 85

O


`\oddsidemargin` 4, 101
`\onecolumn` . §5.1; 2, 21–23, 32, 111, 112, 231, 239, 256, *see also*
`\twocolumn` & `\Ncolumn`

P

page counter .. 2, 4, 24, 25, 63, 64, 73, 89, 107, 260
page list 2, 4, 24, 25, 36, 40, 51, 60, 70–73, 75, 94, 112, 115, 128, 179, 184,

- 189, 198, 215, 243, 259, 260
- page range 36, 189
- page styles *see also* header frame & footer frame
- empty 18, 20, 62, 65, 258
- ffempty [§2.4.2](#); 18, 20, 21, 62, 63–65, 256–258
- ffheadings [§2.4.2](#); 18–20, 60, 63, 64, 65, 209, 211, 226, 257, 258
- ffmyheadings [§2.4.2](#); 18, 21, 63, 64, 65, 257, 258
- ffplain [§2.4.2](#); 18, 20, 63, 65, 257, 258
- headings 18, 63, 65, 258
- myheadings 18, 63, 65, 258
- plain 18, 65, 258
- \pagebreak 38
- \pageref 151
- \pagestyle 21, 257
- \paperheight 251
- \paperwidth 220
- \par 91
- \parbox 56
- \parindent 58, 154
- \parshape [§3.2](#); 5, 91, 92, 93, 183
- \part 92, 235
- pdf-trans.tex 156, 158, 224
- \pdfinfo 159, 160
- pgf package 153, 156, 187
- decorations.text 156
- pgfpicture environment 153, 157, 187
- \pgfpoint 162
- pgfscope environment 163, 164, 213
- pst-char package 156, 158, 224
- ## R
- \raggedleft 160
- \raggedright 160
- \ref 150, 151, 225
- \RefSavedRelativeLocation [§4.3](#); 108, 235, 237
- \relativeframelocation [§4.3](#); 48, 104, 106, 107, 236, 237
- \reldynamicloc [§4.3](#); 106, 236
- \relflowloc [§4.3](#); 107, 236
- \relstaticloc [§4.3](#); 106, 236
- report class 57–59, 202, 203
- \rightmark 64
- ## S
- \SaveRelativeFrame-Location [§4.3](#); 104, 107, 108, 221, 222, 235, 237
- scrbook class 56
- \sdfparindent [§7.2](#); 49, 76, 148, 183, 237
- secnumdepth counter 11, 12, 255, 256
- \section 92, 139, 195, 237
- \sectionmark .. 18, 19, 64, 257, 258
- \setalldynamicframes [§3](#); 70, 237
- \setallflowframes [§3](#); 69, 237

- `\setallstaticframes` §3;
69, 238
- `\setdynamiccontents` §2.4; 4, 52,
65, 238
- `\setdynamicframe` . §3; 60, 70, 85,
141, 238
- `\setffdraftcolor` . §7.1; 147, 238
- `\setffdrafttypeblockcolor`
§7.1; 147, 238
- `\setflowframe` .. §3; 35, 38, 69, 84,
185, 239
- `\setlength` 39
- `\SetOneColumnFrame` §1.2.3;
23, 239
- `\setstaticcontents` §2.3; 4, 8, 9,
42, 43, 48, 189, 239
- `\setstaticframe` §3; 69, 85,
92, 239
- `\setthumtab` §6.1; 142, 239
- `\setthumtabindex` §6.1; 142, 240
- `\SetTwoColumnFrames` ... §1.2.3;
24, 240
- `\set⟨type⟩frame` 70, 184, *see*
 `\setflowframe`,
 `\setdynamicframe` &
 `\setstaticframe`
- `\set⟨type⟩frame` options
 - `angle` §3.1.4; 26, 85
 - `back-color` *see* `backcolor`
 - `back-colour` *see* `backcolor`
 - `backcolor` §3.1.4; 27, 86, 87, 88,
128, 155
 - `backcolour` *see* `backcolor`
 - `border-color` *see* `bordercolor`
 - `border-colour` *see* `bordercolor`
 - `border` §3.1.4; 35, 40, 51, 85, 185
 - `bordercolor` ... §3.1.4; 27, 86, 87, 155
 - `bordercolour` *see* `bordercolor`
 - `clear` ... §3.1.2; 28, 40, 51, 60, 75, 76,
145, 181, 185, 189
 - `evenx` §3.1.3; 4, 56, 81, 138, 184
 - `eveny` §3.1.3; 4, 81, 82, 184
 - `excludepages` §3.1.1; 4, 73
 - `height` §3.1.3; 80, 184
 - `hide` §3.1.1; 4, 21, 63, 64, 75, 196, 200,
226, 257
 - `hidethis` . §3.1.1; 4, 21, 63, 64, 75, 257
 - `html` §3.1.5; 89, 208
 - `alt` §3.1.5; 91
 - `class` §3.1.5; 90
 - `div` §3.1.5; 90
 - `image` §3.1.5; 90, 91
 - `mime-type` §3.1.5; 90
 - `show` §3.1.5; 90
 - `style` §3.1.5; 90
 - `label` §3.1.1; 71
 - `margin` §3.1.3; 78, 185
 - `oddx` §3.1.3; 81, 83, 184
 - `oddy` §3.1.3; 81, 84, 184
 - `offset` ... §3.1.3; 79, 85, 113, 182, 184
 - `pages` §3.1.1; 4, 71
 - `parindent` §3.1.2; 76, 148, 183,

- 184, 237
- shape §3.1.2; 78, 91–93, 154, 180, 185
- style §3.1.2; 19, 61, 76, 77, 78, 145, 185
- text–color *see* textcolor
- text–colour *see* textcolor
- textcolor §3.1.4; 27, 88
- textcolour *see* textcolor
- valign §3.1.2; 78, 181
- width §3.1.3; 79, 184
- x §3.1.3; 81, 133, 184
- y §3.1.3; 81, 132, 184
- \sfswapoddeven ... §3.1.3; 85, 240
- \shadowbox 6, 85
- \Shapepar ... §3.2; 5, 91, 92, 93, 208
- \shapepar ... §3.2; 5, 91, 92, 93, 208
- shapepar package 91–93, 154
- show §8.4.2.2; 175
- \showframebboxfalse §1.4; 30, 240
- \showframebboxtrue §1.4; 30, 240
- \showmarginsfalse §1.4; 30, 241
- \showmarginstrue .. §1.4; 30, 241
- \showtypeblockfalse §1.4; 29, 241
- \showtypeblocktrue §1.4; 29, 241
- \simpar  *see* \FLFsimpar
- special labels ... §2.4; 10, 51, 60, 137, 155
 - evenfooter §2.4.2; 51, 60, 188
 - evenheader §2.4.2; 51, 60, 188
 - eventhumbtabindex⟨*n*⟩ .. §6.1; 51, 137
 - eventhumbtab⟨*n*⟩ §6.1; 51, 137
 - footer §2.4.2; 51, 60, 75, 188
 - header §2.4.2; 51, 60, 75, 188
 - thumbtabindex⟨*n*⟩ §6.1; 51, 137
 - thumbtab⟨*n*⟩ §6.1; 51, 137
- start §8.4.2.2; 176
- static frame 4, 40, 69, 75, 78, 89, 106, 130, 131, 188, 189, 227, 230, 232, 235–237, 246, 249
- \staticaddexclusion ... §3.1.1; 74, 241
- staticcontents environment §2.3; 41, 42, 43, 47, 48, 50, 194, 252
- staticcontents* environment §2.3; 42, 43, 253
- staticfigure environment §1.3; 28, 185, 253
- \staticframe §2.3; 42, 43, 242
- \staticframeevenx §3.1.3; 82, 242
- \staticframeeveny §3.1.3; 83, 242
- \staticframeheight §3.1.3; 80, 242
- \staticframewidth §3.1.3; 80, 242
- \staticframex §3.1.3; 83, 242
- \staticframey §3.1.3; 84, 243
- \staticsetexclusion ... §3.1.1; 74, 243

- `\staticsetpagelist` §3.1.1; 72, 243
 - `\staticswitchoffnext` ... §3.3; 98, 243
 - `\staticswitchoffnextodd` §3.3; 98, 243
 - `\staticswitchoffnextodd-only` §3.3; 98, 243
 - `\staticswitchoffnextonly` §3.3; 98, 244
 - `\staticswitchonnext` §3.3; 97, 244
 - `\staticswitchonnextodd` §3.3; 98, 244
 - `\staticswitchonnextodd-only` §3.3; 98, 244
 - `\staticswitchonnextonly` §3.3; 98, 244
 - `statictable` environment §1.3; 28, 185, 253
 - `\subsectionmark` 18, 19, 64, 65, 258
- T**
- `table` environment 27, 28
 - `table*` environment 27, 32
 - `\tableofcontents` 10–12, 140, 245
 - `\textheight` 2, 31, 189, 249
 - `\textwidth` 2, 31, 189, 250
 - `thisframe` counter . §7.3; 150, 151, *see also* `displayedframe`
 - `\thispagestyle` 21, 257
 - `thumbtab` §6.1; 10–17, 26, 27, 137, 138–144, 150, 192, 196, 200, 226, 235, 237, 239, 240, 245, 246, 255, 259–263
 - `thumbtab` label *see* special labels
 - `\thumbtabformat` .. §6.1; 141, 245
 - `\thumbtabhyperlinkformat` §6.1; 141, 245
 - `\thumbtabindex` §6.1; 140, 245
 - `\thumbtabindexformat` ... §6.1; 141, 245
 - `\thumbtabregularformat` §6.1; 141, 245
 - `\thumbtabwidth` §6.1; 138, 246
 - `tikz` package 134, 154
 - `\topmargin` 2, 250
 - `\twocolumn` §5.1; 2, 3, 21–23, 32, 111, 112, 113, 114, 127, 221, 240, 246, 256, 259, 260, *see also* `\onecolumn` & `\Ncolumn`
 - `\twocolumnbottom` §5.2; 124, 246, 247, 248
 - `\twocolumnbottominarea` §5.2; 117, 124, 246, 247, 248
 - `\twocolumnDbottom` §5.2; 124, 247
 - `\twocolumnDbottominarea` §5.2; 124, 247
 - `\twocolumnDtop` §5.2; 23, 120, 247
 - `\twocolumnDtopinarea` ... §5.2; 119, 247

`\twocolumninarea` ... §5.1; 21, 23,
 114, 115, 248, *see also*
 `\onecolumninarea` &
 `\Ncolumninarea`
`\twocolumnSbottom` §5.2; 124, 248
`\twocolumnSbottominarea`
 §5.2; 123, 248
`\twocolumnStop` §5.2; 23, 120,
 134, 248
`\twocolumnStopinarea` ... §5.2;
 119, 249
`\twocolumntop` §5.2; 119, 247,
 248, 249
`\twocolumntopinarea` §5.2; 116,
 119, 247, 249
`typeblock` 1–4, 29, 31, 35, 40, 51, 101, 102,
 111–113, 115, 118, 119, 121, 122,
 124, 125, 128, 138, 147, 155,
 179–181, 189, 193, 194, 205, 223,
 226, 227, 229, 231, 232, 234, 238,
 246, 249, 250
`\typeblockheight` §1; 2, 31,
 189, 249
`\typeblockoffsety` ... §1; 2, 250
`\typeblockwidth` §1; 2, 31,
 189, 250

U

`\uncover` 165

V

`\vcolumnsep` ... §7.2; 115, 149, 227,
 230, 232, 235, 246, 249, 250
`\verb` 186
`verbatim` 50, 52, 67, 186, 252
`\vNtone` §5.4.1; 129, 250
`\vNtonebottom` §5.4.1; 130, 251
`\vNtonetop` §5.4.1; 130, 251
`\voffset` 2, 250
`\vtwotone` §5.4.1; 129, 250, 251
`\vtwotonebottom` §5.4.1; 129, 130,
 251, 252
`\vtwotonetop` §5.4.1; 129, 130,
 251, 252

